

Running MPAS Part 1: Creating initial conditions and running a basic global simulation

Michael G. Duda
NSF NCAR/MMM



NCAR
OPERATED BY UCAR

Initial conditions for "real-data" simulations

- Processing time-invariant, terrestrial ("static") fields
- Interpolating atmospheric and land-surface fields
- Producing SST and sea-ice update files

Running a basic simulation

There will be many digressions along the way...


Real-data Initial Conditions

- 
- Processing time-invariant fields (“static” file generation)
 - Interpolating atmospheric and land-surface fields
 - Producing SST and sea-ice update files


Running a basic simulation

Real-data ICs: processing static fields


When we talk about time-invariant, “static” fields, what exactly do we mean?




Terrain elevation




Vegetation category




Soil texture category



Sub-grid-scale terrain variance



*Climatological monthly
vegetation fraction*




*Climatological monthly surface
albedo*

These fields can be interpolated once and re-used for any real-data simulation

From where do we obtain the datasets for these “static” fields?

[Home](#)
[News & Events](#)
[Contact](#)
[Support Forum](#)
[Site Map](#)





MPAS Atmosphere

Model for Prediction Across Scales - Atmosphere

Documentation +

Downloads -

Model Source Code

Static Geographic Datasets

Meshes & Mesh Utilities

Idealized Test Cases

Real-data Input

GPU-enabled MPAS-A +

Visualization


News & Events

Publications

[Home](#) / [Model for Prediction Across Scales - Atmosphere](#)
[View source](#)
[GitHub](#)

Model for Prediction Across Scales - Atmosphere

The atmospheric component of MPAS uses an unstructured centroidal Voronoi mesh (grid, or tessellation) and C-grid staggering of the state variables as the basis for the horizontal discretization in the fluid-flow solver. The unstructured variable resolution meshes can be generated having smoothly-varying mesh transitions (see figure (a) below), which ameliorates many issues associated with the traditional mesh refinement strategy of one-way and two-way grid nesting where the transitions are abrupt. The flexibility of the MPAS meshes allows for applications in high-resolution numerical weather prediction (NWP) and regional climate, in addition to global uniform-resolution NWP and climate applications.



Documentation & Resources


- [Overview of MPAS-A](#)
- [MPAS-A User Guide](#)
- [MPAS-A Technical Description](#)
- [MPAS Mesh Specification](#)

Access Code, Data, & Meshes

Information and links to MPAS-A source code, static geographical datasets, meshes, and input files for real-data and idealized test cases

Before creating initial conditions, we need a (horizontal) mesh!

[Home](#)
[News & Events](#)
[Contact](#)
[Support Forum](#)
[Site Map](#)





MPAS Atmosphere

Model for Prediction Across Scales - Atmosphere

Documentation +

Downloads -

Model Source Code

Static Geographic Datasets

Meshes & Mesh Utilities

Idealized Test Cases

Real-data Input

GPU-enabled MPAS-A +

Visualization


News & Events

Publications

[Home](#) / [Model for Prediction Across Scales - Atmosphere](#)
[View source](#)
[GitHub](#)

Model for Prediction Across Scales - Atmosphere

The atmospheric component of MPAS uses an unstructured centroidal Voronoi mesh (grid, or tessellation) and C-grid staggering of the state variables as the basis for the horizontal discretization in the fluid-flow solver. The unstructured variable resolution meshes can be generated having smoothly-varying mesh transitions (see figure (a) below), which ameliorates many issues associated with the traditional mesh refinement strategy of one-way and two-way grid nesting where the transitions are abrupt. The flexibility of the MPAS meshes allows for applications in high-resolution numerical weather prediction (NWP) and regional climate, in addition to global uniform-resolution NWP and climate applications.




Documentation & Resources

- [Overview of MPAS-A](#)
- [MPAS-A User Guide](#)
- [MPAS-A Technical Description](#)
- [MPAS Mesh Specification](#)

Access Code, Data, & Meshes

Information and links to MPAS-A source code, static geographical datasets, meshes, and input files for real-data and idealized test cases

The mesh download page has meshes that have been well-tested



MPAS Atmosphere

Meshes & Mesh Utilities +

Documentation +

Downloads -

Model Source Code

Static Geographic Datasets

Meshes & Mesh Utilities

Idealized Test Cases

Real-data Input

GPU-enabled MPAS-A +

Visualization

News & Events

Publications

Quasi-uniform Meshes and Static Fields

Click on links in the "File" column below to download the mesh and static file needed.

Resolution	# of horizontal grid cells	File
480 km	2562	480-km mesh (1.5 MB) 480-km static file (1.0 MB)
384 km	4002	384-km mesh (2.4 MB) 384-km static file (2.3 MB)
240 km	10242	240-km mesh (6.3 MB) 240-km static file (4.0 MB)
120 km	40962	120-km mesh (25.7 MB) 120-km static file (16.2 MB)
60 km	163842	60-km mesh (106 MB) 60-km static file (69.6 MB)
48 km	256002	48-km mesh (182 MB) 48-km static file (174 MB)
30 km	655362	30-km mesh (436 MB) 30-km static file (296 MB)
24 km	1024002	24-km mesh (685 MB) 24-km static file (525 MB)
15 km	2621442	15-km mesh (1659 MB) 15-km static file (1366 MB)

Filenames of the meshes that are found on the download page include:

```
x1.40962.grid.nc  
x1.163842.grid.nc  
x1.655362.grid.nc  
x1.2621442.grid.nc  
x1.5898242.grid.nc  
x4.163842.grid.nc  
x4.535554.grid.nc  
x5.6488066.grid.nc
```

How does one
interpret these
cryptic names?

Filenames of the meshes that are found on the download page include:

x1_40962.grid.nc
x1_163842.grid.nc
x1_655362.grid.nc
x1_2621442.grid.nc
~~x1_5898242.grid.nc~~
x4_163842.grid.nc
x4_535554.grid.nc
x5_6488066.grid.nc

Refinement factor:

x1 = no refinement (quasi-uniform)

x4 = refinement by a factor of 4


x5 = refinement by a factor of 5

Real-data ICs: processing static fields

Filenames of the meshes that are found on the download page include:

x1 40962
x1 163842
x1 655362
x1 2621442
x1 5898242
x4 163842
x4 535554
x5 6488066

Total number of cells in the mesh



When downloading a mesh, you'll get the mesh itself as well as various *mesh (graph) partition files*.

For example, the x1.40962 mesh (about 120-km resolution) is provided with the following files:

- x1.40962.grid.nc – the mesh itself
- x1.40962.graph.info – the mesh connectivity graph
- x1.40962.graph.info.part.2 – pre-computed partitioning for 2 MPI tasks
- x1.40962.graph.info.part.8 – pre-computed partitioning for 8 MPI tasks
- x1.40962.graph.info.part.16 – pre-computed partitioning for 16 MPI tasks
- ...

We'll say more about partition files when talking about running the model, and also when talking about MPAS meshes

Recall from the lecture about compiling MPAS that there are two executables we need to initialize and run an MPAS-Atmosphere simulation:

`init_atmosphere_model`

- Handles all stages of processing real-data initial conditions
- Handles processing of SST and sea-ice update files
- Handles generation of lateral boundary conditions
- Handles generation of various idealized initial conditions

`atmosphere_model`

- The model itself, responsible for performing integration/simulation given any source of initial conditions

Real-data ICs: processing static fields

How does the 'init_atmosphere' core manage to combine all of this functionality into one program?

- The key idea is that `init_atmosphere_model` may be run in stages using different options

```
&nhyd_model
  config_init_case = 7
  ...
/

&preproc_stages
  config_static_interp = true
  config_native_gwd_static = true
  config_vertical_grid = false
  config_met_interp = false
  config_input_sst = false
  config_frac_seaice = false
/
```

2 = ideal baroclinic wave
 4 = ideal squall line
 5 = ideal supercell
 6 = ideal mountain wave
7 = real-data initialization
 8 = surface update file creation
 9 = lateral boundary conditions

Only used for real-data cases to control, e.g., whether we interpolate static fields, compute fields for GWDO scheme, interpolate meteorological data, etc.

Generally, there are two files that must be edited every time the `init_atmosphere_model` program is run:

`namelist.init_atmosphere`


- Fortran *namelist* file
- Determines which “case” will be prepared (e.g., idealized cases, real-data case)
- Determines sub-options for the selected initialization case

`streams.init_atmosphere`

- XML file
- Specifies which netCDF files will be read and written by the `init_atmosphere_model` program

Real-data ICs: processing static fields

Input and output files when producing a “static” file:



Key settings in the `namelist.init_atmosphere` file:

```
&nhyd_model
  config_init_case = 7
/

&data_sources
  config_geog_data_path = '/glade/work/duda/mpas_static/'
/

&preproc_stages
  config_static_interp = true
  config_native_gwd_static = true
  config_vertical_grid = false
  config_met_interp = false
  config_input_sst = false
  config_frac_seaice = false
/
```

Real-data ICs: processing static fields

Key settings in the `streams.init_atmosphere` file:

```
<immutable_stream name="input"
                  type="input"
                  filename_template="x1.40962.grid.nc"
                  input_interval="initial_only" />

<immutable_stream name="output"
                  type="output"
                  filename_template="x1.40962.static.nc"
                  packages="initial_conds"
                  output_interval="initial_only" />
```

The result should be a “static” netCDF file with

- terrain
- land use category
- soil category
- climatological albedo
- climatological vegetation fraction
- sub-grid-scale orography statistics for the GWDO scheme

Also, the radius of the SCVT mesh should be 6371229.0 m!

Real-data ICs: processing static fields

Look for messages like the following in the `log.init_atmosphere.0000.out` file:

```
--- enter subroutine init_atm_static:
Using GMTED2010 terrain dataset
/shared/WPS_GEOG/topo_gmted2010_30s/00001-01200.00001-01200
/shared/WPS_GEOG/topo_gmted2010_30s/01201-02400.00001-01200
/shared/WPS_GEOG/topo_gmted2010_30s/02401-03600.00001-01200
```

Computing GWDO static fields on the native MPAS mesh

```
--- Using GMTED2010 terrain dataset for GWDO static fields
```

```
-----
Total log messages printed:
    Output messages =                3067
    Warning messages =                10
    Error messages =                  0
    Critical error messages =         0
-----
```

At this point, you may ask:

- If the "static" fields are independent of the starting time of a simulation,
- couldn't the MPAS developers do the preceding steps once and make the resulting static files available for everyone?

Quasi-uniform Meshes and Static Fields

Click on links in the "File" column below to download the mesh and static file needed.

Resolution	# of horizontal grid cells	File
480 km	2562	Download the 480-km mesh (1.5 MB) Download the 480-km static file (1.0 MB)
384 km	4002	Download the 384-km mesh (2.4 MB) Download the 384-km static file (2.3 MB)
240 km	10242	Download the 240-km mesh (6.3 MB) Download the 240-km static file (4.0 MB)
120 km	40962	Download the 120-km mesh (25.7 MB) Download the 120-km static file (16.2 MB)
60 km	163842	Download the 60-km mesh (106 MB) Download the 60-km static file (69.6 MB)
48 km	256002	Download the 48-km mesh (182 MB) Download the 48-km static file (174 MB)
30 km	655362	Download the 30-km mesh (436 MB) Download the 30-km static file (296 MB)
24 km	1024002	Download the 24-km mesh (685 MB) Download the 24-km static file (525 MB)
15 km	2621442	Download the 15-km mesh (1659 MB) Download the 15-km static file (1366 MB)

The mesh download page has links to "static" files for all quasi-uniform meshes

Real-data Initial Conditions

- 
- Processing time-invariant fields (“static” file generation)
 - Interpolating atmospheric and land-surface fields
 - Producing SST and sea-ice update files

Running a basic simulation

Creating idealized initial conditions

- 3-d baroclinic wave test case
- 3-d supercell test case
- 2-d mountain wave test case

Digression: “intermediate” data files

Time-varying meteorological and land-surface fields in MPAS-Atmosphere are interpolated from *intermediate* files produced by the **ungrib** component of the **WRF Pre-processing System**.

The practice exercises will give you a chance to create intermediate files

- Additional details may be found in the links, below

WRF Model web page: <http://www2.mmm.ucar.edu/wrf/users/>

WRF Users' guide:


https://www2.mmm.ucar.edu/wrf/users/wrf_users_guide/build/html/index.html

WPS source code: <https://github.com/wrf-model/WPS>

Tutorial slides for running ungrib:

http://www2.mmm.ucar.edu/wrf/users/tutorial/201801/wps_general.pdf

Input and output files when producing an “init” file:



Key settings in the `namelist.init_atmosphere` file:

```
&nhyd_model
  config_init_case = 7
  config_start_time = '2014-09-10_00:00:00'
/

&dimensions
  config_nvertlevels = 55
  config_nsoillevels = 4
  config_nfglevels = 38
  config_nfgsoillevels = 4
/

&data_sources
  config_met_prefix = 'GFS'
/
```


Key settings in the `namelist.init_atmosphere` file (*cont.*):

```
&vertical_grid
  config_ztop = 30000.0
  config_nsmterrain = 1
  config_smooth_surfaces = true
  config_dzmin = 0.3
  config_nsm = 30
  config_tc_vertical_grid = true
  config_blend_bdy_terrain = false
/
&preproc_stages
  config_static_interp = false
  config_native_gwd_static = false
  config_vertical_grid = true
  config_met_interp = true
  config_input_sst = false
  config_frac_seaice = true
/
```

Key settings in the `streams.init_atmosphere` file:

```
<immutable_stream name="input"  
    type="input"  
    filename_template="x1.40962.static.nc"  
    input_interval="initial_only" />  
  
<immutable_stream name="output"  
    type="output"  
    filename_template="x1.40962.init.nc"  
    packages="initial_conds"  
    output_interval="initial_only" />
```

The result should be a “init” netCDF file with

- everything from the “static” file
- 3-d vertical grid information
- 3-d potential temperature (*theta*)
- 3-d winds (*u* and *w*)
- 3-d water vapor mixing ratio (q_v)
- 3-d soil moisture
- 3-d soil temperature

Look for messages like the following in the `log.init_atmosphere.0000.out` file:

```
real-data GFS test case
Using option 'linear' for vertical extrapolation of temperature
max ter = 5393.19321458650
Setting up vertical levels as in 2014 TC experiments
```

```
--- config_tc_vertical_grid = T
--- als      = 0.7500000000000000E-01
--- alt      = 1.7000000000000000
--- zetal    = 0.7500000000000000
```

```
Interpolating TT at 27 1000.000000000000
Interpolating U at 27 1000.000000000000
Interpolating V at 27 1000.000000000000
Interpolating RH at 27 1000.000000000000
Interpolating GHT at 27 1000.000000000000
*****
Found 38 levels in the first-guess data
*****
```


Real-data Initial Conditions

- Processing time-invariant fields (“static” file generation)
- Interpolating atmospheric and land-surface fields
- Producing SST and sea-ice update files

Running a basic simulation

Producing SST and sea-ice update files

Input and output files when producing an SST update file:



Key settings in the `namelist.init_atmosphere` file:

```
&nhyd_model
  config_init_case = 8
  config_start_time = '2014-09-10_00:00:00'
  config_stop_time = '2014-09-20_00:00:00'
/
&data_sources
  config_sfc_prefix = 'SST'
  config_fg_interval = 86400
/
&preproc_stages
  config_static_interp = false
  config_native_gwd_static = false
  config_vertical_grid = false
  config_met_interp = false
  config_input_sst = true
  config_frac_seaice = true
/
```


Producing SST and sea-ice update files

Key settings in the `streams.init_atmosphere` file:

```
<immutable_stream name="input"  
    type="input"  
    filename_template="x1.40962.static.nc"  
    input_interval="initial_only" />  
  
<immutable_stream name="surface"  
    type="output"  
    filename_template="x1.40962.sfc_update.nc"  
    filename_interval="none"  
    packages="sfc_update"  
    output_interval="86400" />
```

Real-data ICs: processing static fields

Look for messages like the following in the `log.init_atmosphere.0000.out` file:

```
real-data surface (SST) update test case
Processing file SST:2014-09-10_00
Processing file SST:2014-09-11_00
Processing file SST:2014-09-12_00
Processing file SST:2014-09-13_00
Processing file SST:2014-09-14_00
Processing file SST:2014-09-15_00
Processing file SST:2014-09-16_00
Processing file SST:2014-09-17_00
Processing file SST:2014-09-18_00
Processing file SST:2014-09-19_00
Processing file SST:2014-09-20_00
```

```
-----
Total log messages printed:
  Output messages =                144
  Warning messages =                0
  Error messages =                 0
  Critical error messages =         0
-----
```

Real-data Initial Conditions

- Processing time-invariant fields (“static” file generation)
- Interpolating atmospheric and land-surface fields
- Producing SST and sea-ice update files




 Running a basic simulation

Running the MPAS-Atmosphere model

The same `atmosphere_model` executable can be used for either real-data or idealized simulations

Given initial conditions (e.g., `x1.40962.init.nc`), all that is needed to run the model is to:

1. Edit the `namelist.atmosphere` file to set model timestep, mixing and damping parameters, physics options, etc.
2. Edit the `streams.atmosphere` file to specify the name of the input initial conditions file and the frequency of model history files
3. Ensure that the proper mesh partition file (e.g., `x1.40962.graph.info.part.64`) is present
4. Run `atmosphere_model`



Running the MPAS-Atmosphere model

Before running the model itself (`atmosphere_model`), verify that the following namelist options have been properly set:

- **config_start_time** – The starting time of the simulation, which should either match the time in the initial conditions files or a *model restart file*.
- **config_dt** – The model timestep, in seconds; try starting with a timestep of between 5 and 6 times the minimum model grid spacing in kilometers; also ensure that model output interval is evenly divided by the timestep


Besides these crucial namelist options, ensure that the names of input and output files are correctly set in the `streams.atmosphere` file!

Digression: Mesh partition files

MPAS meshes must be partitioned using *Metis* in order for MPAS to allow simulations to run in parallel

However, the meshes available from the MPAS-Atmosphere download page are provided with several pre-computed partition files

- **In many cases, it may not be necessary for you to run Metis yourself; just use a pre-computed partitioning**



For example, the x1.40962 mesh (about 120-km resolution) is provided with the following files:

- x1.40962.grid.nc – the mesh itself
- x1.40962.graph.info – the mesh connectivity graph
- x1.40962.graph.info.part.2 – pre-computed partitioning for 2 MPI tasks
- x1.40962.graph.info.part.8 – pre-computed partitioning for 8 MPI tasks
- x1.40962.graph.info.part.16 – pre-computed partitioning for 16 MPI tasks

...

Running the MPAS-Atmosphere model

As the model runs, information about the progress of the model is written to the file `log.atmosphere.0000.out`

You can *tail* this file to check on model progress, e.g.,

```
$ tail -f log.atmosphere.0000.out
```

```
Begin timestep 2017-06-12_01:00:00
--- time to run the LW radiation scheme L_RADLW = T
--- time to run the SW radiation scheme L_RADSW = T
--- time to run the convection scheme L_CONV      = T
--- time to apply limit to accumulated rainc and rainnc L_ACRAIN      = F
--- time to apply limit to accumulated radiation diags. L_ACRADT      = F
--- time to calculate additional physics_diagnostics                  = F
    split dynamics-transport integration                        3

global min, max w   -0.4467210      1.098162
global min, max u   -89.13145      88.83957
Timing for integration step:      0.3368 s
```

Above: Example output for a timestep in the log file from a typical model run.

One final, important note...

If there are any errors reported in the `log.init_atmosphere.0000.out` or `log.atmosphere.0000.out` files, look for `log.*.err` files, and have a closer look!

```
-----
Total log messages printed:
  Output messages =                46
  Warning messages =                0
  Error messages =                  0
  Critical error messages =         1
-----
```

```
-----
Beginning MPAS-init_atmosphere Error Log File for task      0 of      1
  Opened at 2018/07/27 16:35:58
-----

CRITICAL ERROR: Could not open input file 'x1.40926.init.nc' to read
mesh fields
Logging complete.  Closing file at 2018/07/27 16:35:58
```

Summary

- Begin by downloading static geographical datasets and a mesh from the MPAS-A download page
- For real-data initial conditions:
 - Interpolate time-invariant ("static") terrestrial fields
 - Obtain an "intermediate" file with atmospheric and soil state
 - Generate vertical grid and interpolate time-varying fields
- Run the simulation
 - At a minimum, set starting time and integration step in the `namelist.atmosphere` file
 - Ensure you have a mesh partition file corresponding to # of MPI tasks
 - Set input and output filenames in the `streams.atmosphere` file