




# The WRF Preprocessing System: Description of General Functions

Michael Duda



---

The WRF Users' Basic Tutorial  
21 – 25 July 2014, Boulder, CO

\*NCAR is sponsored by the  
National Science Foundation

# Purpose of this Lecture


---

In this lecture, our goals are to:

- 1) Understand the purpose of the WPS
  - 2) Learn what each component of the WPS does
  - 3) Understand why the components work as they do
- 
- The details of *actually running* the WPS are covered this afternoon
  - *Advanced features* of the WPS are described on Thursday



# WRF Modeling System Flowchart



# Purpose of the WPS



---

The purpose of the WPS is to prepare input to WRF for real-data simulations:


1. Defines simulation coarse domain and ARW nested domains
2. Computes latitude, longitude, map scale factors, and Coriolis parameters at every grid point
3. Interpolates time-invariant terrestrial data to simulation grids (e.g., terrain height and soil type)
4. Interpolates time-varying meteorological fields from another model onto simulation domains




# WPS Program Flowchart



# The *geogrid* program



geogrid: think geographical



# The *geogrid* program

---

- For WRF model domains, geogrid defines:
  - ☒ Map projection (all domains must use the same projection)
  - ☒ Geographic location of domains
  - ☒ Dimensions of domains
- Geogrid provides values for static (time-invariant) fields at each model grid point
  - ☒ Compute latitude, longitude, map scale factor, and Coriolis parameters at each grid point
  - ☒ Horizontally interpolate static terrestrial data (e.g., topography height, land use category, soil type, vegetation fraction, monthly surface albedo)



# Geogrid: Defining model domains


---

- First, we choose a map projection to use for the domains; why?
  - ☒ The real earth is (roughly) an ellipsoid
  - ☒ But WRF computational domains are defined by rectangles in the plane
- ARW can use any of the following projections:
  1. Lambert conformal
  2. Mercator
  3. Polar stereographic
  4. Latitude–longitude (for global domain, you *must* choose this projection!)








# ARW Projections: Lambert Conformal




Lambert Conformal




- Well-suited for mid-latitudes
  - Domain cannot contain either pole
  - Domain cannot be periodic in west-east direction
  - Either one or two *true latitudes* may be specified
- ☒ If two are given, the order doesn't matter






# ARW Projections: Mercator




- Well-suited for low-latitudes
  - May be used for “channel” domain (periodic domain in west-east direction)
  - A single true latitude is specified
-  Cylinder intersects the earth's surface at  $\pm$  true lat




Mercator




# ARW Projections: Polar Stereographic



- Good for high-latitude domains, especially if domain must contain a pole
- A single true latitude is specified






# ARW Projections: Cylindrical Equidistant



- Required for global domains
- May be used for regional domains
- Can be used in its normal or rotated aspect

Cylindrical Equidistant



# Why do map projections matter?

---

Each choice of map projection and associated parameters distorts distances at a given point on the globe differently

Geographic grid distance in WRF at a point is given by

$$\Delta x_{\text{geographical}} = \Delta x_{\text{nominal}} / m$$

where  $m$  is a *map scale factor*.

*Maximum stable timestep in WRF is determined by geographic grid distance, not nominal (i.e., namelist) grid distance!*

Map scale factor is a 2-d field available in the geogrid output files

- Can easily check min/max map scale factor using, e.g., ncview!




# Geogrid: Defining Model Domains


---

- Define projection of domains using a subset of the following parameters
  - ☒ **MAP\_PROJ**: ‘lambert’, ‘mercator’, ‘polar’, or ‘lat–lon’
  - ☒ **TRUELAT1**: First true latitude
  - ☒ **TRUELAT2**: Second true latitude (*only for Lambert conformal*)
  - ☒ **POLE\_LAT, POLE\_LON**: Location of North Pole in WRF computational grid (*only for ‘lat–lon’*)
  - ☒ **STAND\_LON**: The meridian parallel to y–axis
- All parameters reside in the file *namelist.wps*

*See p. 3–9 and 3–43*



# Geogrid: Defining ARW Domains






# Geogrid: Defining Model Domains

---


- Define the area covered (dimensions and location) by coarse domain using the following:
  - ❏ REF\_LAT, REF\_LON: The (lat,lon) location of a known location in the domain (*by default, the center point of the domain*)
  - ❏ DX, DY: Grid distance where map factor = 1
    - For Lambert, Mercator, and polar stereographic: **meters**
    - For (rotated) latitude–longitude: **degrees**
  - ❏ E\_WE: Number of velocity points in west–east direction
  - ❏ E\_SN: Number of velocity points in south–north direction

*See p. 3–13 and 3–42*






# Geogrid: Defining ARW Domains



In ARW,  $(REF\_LAT, REF\_LON)$  can refer to an arbitrary point in the domain by using the variables  $REF\_X$  and  $REF\_Y$

*See p. 3-44*



# Geogrid: Nesting Basics


---

- A *nested domain* is a domain that is wholly contained within its *parent domain* and that receives information from its parent, and that may also feed information back to its parent
  - ☒ A nested domain has exactly one *parent*
  - ☒ A domain may have one or more *children*
- 2-way nests on the same *nesting level* must not overlap in coverage!





# Geogrid: Nesting Example

Example configuration – 4 domains



Each domain is assigned a *domain ID #*



# Geogrid: Defining Nested Domains


---

- Define the dimensions and location of nested domains using:
  - ❑ **PARENT\_ID**: Which domain is the parent?
  - ❑ **PARENT\_GRID\_RATIO**: What is the ratio of grid spacing in parent to grid spacing in this nest?
  - ❑ **I\_PARENT\_START**:  $i$ -coordinate in parent of this nest's lower-left corner
  - ❑ **J\_PARENT\_START**:  $j$ -coordinate in parent of this nest's lower-left corner
  - ❑ **E\_WE**: Number of velocity points in west-east direction
  - ❑ **E\_SN**: Number of velocity points in south-north direction


*See p. 3-20 and 3-42*



# Geogrid: Defining Nested Domains




The grid spacing ( $dx$ ) of domain 2 is determined by grid spacing of domain 1 and the *parent\_grid\_ratio*



# Geogrid: Nesting example

Assuming *parent\_grid\_ratio* = 3




In ARW, nest dimensions must satisfy

$$\frac{e_{we} - 1}{parent\_grid\_ratio} = n_i$$

$$\frac{e_{sn} - 1}{parent\_grid\_ratio} = n_j$$


where  $n_i$  and  $n_j$  are any integers.




# Geogrid: Interpolating Static Fields

---


- Given definitions of all computational grids, geogrid interpolates terrestrial, time-invariant fields
  - ☒ Topography height
  - ☒ Land use categories
  - ☒ Soil type (top layer & bottom layer)
  - ☒ Annual mean soil temperature
  - ☒ Monthly vegetation fraction
  - ☒ Monthly surface albedo



# Geogrid: Interpolating Static Fields



In general, source data are given on a different projection from the model grid






# Geogrid: Interpolation Options

---

- 4-point bilinear
- 16-point overlapping parabolic
- 4-point average (simple or weighted)
- 16-point average (simple or weighted)
- Grid cell average
- Nearest neighbor
- Breadth-first search

*See p. 3-55*



# Why have so many interpolation options?

---

- Different interpolators work best for different fields and different relative grid resolutions
  - ☒ Some interpolators preserve positive definiteness
  - ☒ Some interpolators produce “smoother” fields
  - ☒ Some interpolators are best suited for discrete or categorical fields
  - ☒ Some are good when going from a fine grid to a coarse grid
- Having a choice of how to interpolate fields is good!
  - ☒ *We'll see in Thursday's WPS lecture how several different options can be used for different regions of the same field*



# Geogrid: Program Flexibility

---

- *geogrid* is flexible enough to ingest and interpolate new static fields
  - ☐ handles either continuous or categorical fields
- New data sets must be written to simple binary format
- User needs to add an entry to the file  
GEOGRID.TBL







# Geogrid: Program Output

---


- The parameters defining each domain, plus interpolated static fields, are written using the WRF I/O API
  - ☒ One file per domain for ARW
- Filenames: `geo_em.d0n.nc`  
(where *n* is the domain ID number)
- Example:
  - `geo_em.d01.nc`
  - `geo_em.d02.nc` (nest)
  - `geo_em.d03.nc` (nest)




# Geogrid: Example Output Fields



# The *ungrib* program



ungrib: think un+grib



# What is a GRIB file, anyway?

---

- GRIB is a WMO standard file format for storing regularly-distributed (e.g., gridded) fields
  - ☐ “General Regularly-distributed Information in Binary”
- Fields within a GRIB file are compressed with a lossy compression
  - ☐ Think of truncating numbers to a fixed number of digits
- A record-based format
- Fields in a file are identified only by code numbers
  - ☐ These numbers must be referenced against an external table to determine the corresponding field



# The *ungrib* program

---

- Read GRIB Edition 1 and GRIB Edition 2 files
- Extract meteorological fields
- If necessary, derive required fields from related ones
  - ☐ E.g., Compute RH from T, P, and Q
- Write requested fields to an intermediate file format






# Ungrib: Vtables

---

How does ungrib know which fields to extract?

Using Vtables (think: Variable tables)

- Vtables are files that give the GRIB codes for fields to be extracted from GRIB input files
- One Vtable for each source of data
- Vtables are provided for: NAM 104, NAM 212, GFS, AGRMET, and others




# Ungrib: Example Vtable

GRIB1 Param	Level Type	From Level1	To Level2	UNGRIB Name	UNGRIB Units	UNGRIB Description
11	100	*		T	K	Temperature
33	100	*		U	m s-1	U
34	100	*		V	m s-1	V
52	100	*		RH	%	Relative Humidity
7	100	*		HGT	m	Height
11	105	2		T	K	Temperature at 2 m
52	105	2		RH	%	Relative Humidity at 2 m
33	105	10		U	m s-1	U at 10 m
34	105	10		V	m s-1	V at 10 m
1	1	0		PSFC	Pa	Surface Pressure
130	102	0		PMSL	Pa	Sea-level Pressure
144	112	0	10	SM000010	kg m-3	Soil Moist 0-10 cm below grn layer (Up)
144	112	10	40	SM010040	kg m-3	Soil Moist 10-40 cm below grn layer
144	112	40	100	SM040100	kg m-3	Soil Moist 40-100 cm below grn layer
144	112	100	200	SM100200	kg m-3	Soil Moist 100-200 cm below gr layer
85	112	0	10	ST000010	K	T 0-10 cm below ground layer (Upper)
85	112	10	40	ST010040	K	T 10-40 cm below ground layer (Upper)
85	112	40	100	ST040100	K	T 40-100 cm below ground layer (Upper)
85	112	100	200	ST100200	K	T 100-200 cm below ground layer (Bottom)
91	1	0		SEAICE	proprtn	Ice flag
81	1	0		LANDSEA	proprtn	Land/Sea flag (1=land,2=sea in GRIB2)
7	1	0		HGT	m	Terrain field of source analysis
11	1	0		SKINTEMP	K	Skin temperature (can use for SST also)
65	1	0		SNOW	kg m-2	Water equivalent snow depth
223	1	0		CANWAT	kg m-2	Plant Canopy Surface Water
224	1	0		SOILCAT	Tab4.213	Dominant soil type category
225	1	0		VEGCAT	Tab4.212	Dominant land use category



# Ungrib: GRIB2 Vtable Entries

metgrid	GRIB2	GRIB2	GRIB2	GRIB2
Description	Discp	Catgy	Param	Level
Temperature	0	0	0	100
U	0	2	2	100
V	0	2	3	100
Relative Humidity	0	1	1	100
Height	0	3	5	100
Temperature at 2 m	0	0	0	103
Relative Humidity at 2 m	0	1	1	103
U at 10 m	0	2	2	103
V at 10 m	0	2	3	103
Surface Pressure	0	3	0	1
Sea-level Pressure	0	3	1	101
Soil Moist 0-10 cm below grn layer (Up)	2	0	192	106
Soil Moist 10-40 cm below grn layer	2	0	192	106
Soil Moist 40-100 cm below grn layer	2	0	192	106
Soil Moist 100-200 cm below gr layer	2	0	192	106
Soil Moist 10-200 cm below gr layer	2	0	192	106
T 0-10 cm below ground layer (Upper)	0	0	0	106
T 10-40 cm below ground layer (Upper)	0	0	0	106
T 40-100 cm below ground layer (Upper)	0	0	0	106
T 100-200 cm below ground layer (Bottom)	0	0	0	106
T 10-200 cm below ground layer (Bottom)	0	0	0	106
Ice flag	0	2	0	1
Land/Sea flag (1=land, 0 or 2=sea)	2	0	0	1
Terrain field of source analysis	2	0	7	1
Skin temperature (can use for SST also)	0	0	0	1
Water equivalent snow depth	0	1	13	1
Dominant soil type cat.(not in GFS file)	2	3	0	1
Dominant land use cat. (not in GFS file)	2	0	198	1



# Ungrib: Vtables


---

What if a data source has no existing Vtable?

## Create a Vtable

- Get a listing of GRIB codes for fields in the source
  - ☐ Check documentation from originating center or use utility such as *wgrib*, *g1print*, *g2print*
- Use existing Vtable as a template
- Check documentation in Chapter 3 of the Users' Guide for more information about Vtables

See p. 3–35




# Ungrib: Intermediate File Format

---

- After extracting fields listed in Vtable, ungrib writes those fields to intermediate format
- For meteorological data sets not in GRIB format, the user may write to intermediate format directly

*See p. 3–33*

- ☐ Allows WPS to ingest new data sources; basic programming required of user
- ☐ Simple intermediate file format is easily read/written using routines from WPS ([read\\_met\\_module.F](#) and [write\\_met\\_module.F](#))




# Ungrib: Program Output


---

- Output files named *FILE:YYYY-MM-DD\_HH*
  - ☒ *YYYY* is year of data in the file; *MM* is month; *DD* is day; *HH* is hour
  - ☒ All times are UTC
- Example:  
*FILE:2007-07-24\_00*  
*FILE:2007-07-24\_06*  
*FILE:2007-07-24\_12*

ungrib can also write intermediate files in the MM5 or WRF SI format!  
*(To allow for use of GRIB2 data with MM5, for example)*



# The *metgrid* program



metgrid: think meteorological



# The *metgrid* program

---


- Horizontally interpolate meteorological data (*extracted by ungrib*) to simulation domains (*defined by geogrid*)
  - ☒ Masked interpolation for masked fields
  - ☒ *Can process both isobaric and native vertical coordinate data sets*
- Rotate winds to WRF grid
  - ☒ i.e., rotate so that U-component is parallel to x-axis, V-component is parallel to y-axis






# Metgrid: ARW Grid Staggering

- For ARW, wind U–component interpolated to “u” staggering
- Wind V–component interpolated to “v” staggering
- Other meteorological fields interpolated to “ $\theta$ ” staggering by default (*can change this!*)



*A single ARW grid cell, with “u”, “v”, and “ $\theta$ ” points labeled.*



# Metgrid: Interpolation Options\*

---

- 4-point bilinear
- 16-point overlapping parabolic
- 4-point average (simple or weighted)
- 16-point average (simple or weighted)
- Grid cell average
- Nearest neighbor
- Breadth-first search

\* These are the same options available for geogrid!




# Metgrid: Masked Interpolation

---

- *Masked fields* may only have valid data at a subset of grid points
  - ☐ E.g., SST field only valid on water points
- When metgrid interpolates masked fields, it must know which points are invalid (masked)
  - ☐ Can use separate mask field (e.g., LANDSEA)
  - ☐ Can rely on special values (e.g.,  $1 \times 10^{30}$ ) in field itself to identify masked grid points



# Metgrid: Masked Interpolation




- = valid source data
- = masked/invalid data

Suppose we need to interpolate to point X


- Using **red** points as valid data can give a bad interpolated value!
- Masked interpolation only uses valid **blue** points to interpolate to X

*Not every interpolation option can handle masked points; we'll address this issue in the advanced WPS lecture*




# Example: Masked Interpolation

---



Skin temperature field interpolated from GFS 0.5-deg field with no mask using a sixteen-point interpolator.




Skin temperature field interpolated using masks: GFS water points interpolated to model water points, GFS land points interpolated to model land points.




# Metgrid: Wind Rotation

---


- Input wind fields (U-component + V-component) are either:
  - ☒ **Earth-relative:** U-component = westerly component; V-component = southerly component
  - ☒ **Relative to source grid:** U-component (V-component) parallel to source model x-axis (y-axis)
- WRF expects wind components to be relative to the simulation grid



# Metgrid: Wind Rotation Example




A wind vector, shown in terms of its U and V components with respect to the source grid.



The same vector, in terms of its U and V components with respect to the WRF simulation grid.

This process may require *two* rotations: one from source grid to earth grid and a second from earth grid to WRF grid



# Metgrid: Constant Fields

---

- For short simulations, some fields may be constant
  - ☐ E.g., SST or sea-ice fraction
- Use namelist option `CONSTANTS_NAME` option to specify such fields:
  - ☐ `CONSTANTS_NAME = 'SST_FILE:2007-07-24_00'`





# Metgrid: Program Output






---

- For coarse domain, one file per time period
  - ☐ In ARW, we also get the first time period for all nested grids
- Files contain static fields from geogrid plus interpolated meteorological fields
- Filenames:

ARW: `met_em.d0n.YYYY-MM-DD_HH:mm:ss.nc`  
(where  $n$  is the domain ID number)





# Metgrid: Example Output




# WPS Summary

---



# And finally...

Vertical interpolation to WRF eta levels is performed in the *real* program



# Questions?

