


The WRF Pre-Processing System (WPS): Fundamental Capabilities

Michael Duda

*NCAR-NCAS WRF Tutorial
7 – 10 October 2019*



WRF Modeling System Flowchart



The WPS is used to configure real-data simulations


Overview

This lecture focuses on the basic use of the WPS to:

- Define a single simulation domain
 - The setup of *nested domains* is covered in a talk tomorrow morning
 - Preprocess time-varying atmospheric and land-surface datasets
 - Horizontally interpolate datasets for use as initial and boundary conditions for WRF
- Practical details of *actually running* the WPS are covered this afternoon and in a live demo tomorrow
- *Advanced features* of the WPS are described on Wednesday


WPS Program Flowchart

External Data
Sources



The *geogrid* Program


External Data
Sources



geogrid: think geographical

The *geogrid* Program

Let's suppose we wish to perform a simulation for the domain below...



- Where is this domain located?
- What area does the domain cover?
- How well do we resolve the atmosphere and land surface (horizontally)?
- What sources of data do we use for topography, vegetation categories, and soil categories?

Using the geogrid program, we answer these questions from the perspective of the WRF model.


The *geogrid* Program

- We use the geogrid program to define:
 - Map projection (all domains must use the same projection)
 - Geographic location of domains
 - Dimensions of domains
 - Horizontal resolution of domains
- Geogrid provides values for static (time-invariant) fields at each model grid point
 - Compute latitude, longitude, map scale factor, and Coriolis parameters at each grid point
 - Horizontally interpolate static terrestrial data (e.g., topography height, land use category, soil type, vegetation fraction, monthly surface albedo) from global datasets


Geogrid: Defining Model Domains

- First, we choose a map projection to use for the domains; why?
 - The real earth is (roughly) an ellipsoid
 - But WRF computational domains are defined by rectangles in the plane
- ARW can use any of the following projections:
 1. Lambert conformal
 2. Mercator
 3. Polar stereographic
 4. Latitude-longitude (for global domain, you *must* choose this projection!)


Projections: Lambert Conformal Conic



Lambert Conformal




- Well-suited for mid-latitudes
- Domain cannot contain either pole
- Domain cannot be periodic in west-east direction
- Either one or two *true latitudes* may be specified
 - If two are given, the order doesn't matter




Projections: Mercator




- Well-suited for low-latitudes
- May be used for “channel” domain (periodic domain in west-east direction)
- A single true latitude is specified
 - Cylinder intersects the earth’s surface at +/- truelat




Projections: Polar Stereographic



- Good for high-latitude domains, especially if domain must contain a pole
- A single true latitude is specified




Projections: Cylindrical Equidistant



- Required for global domains
- May be used for regional domains
- Can be used in its normal or rotated aspect

Cylindrical Equidistant



Geogrid: Defining model domains

- Define projection of domains using a subset of the following parameters
 - **MAP_PROJ**: ‘lambert’, ‘mercator’, ‘polar’, or ‘lat–lon’
 - **TRUELAT1**: First true latitude
 - **TRUELAT2**: Second true latitude (*only for Lambert conformal*)
 - **POLE_LAT**, **POLE_LON**: Location of North Pole in WRF computational grid (*only for ‘lat–lon’*)
 - **STAND_LON**: The meridian parallel to y -axis
- All parameters reside in the file *namelist.wps*

See p. 3-9 and 3-43

Why do map projections matter?

Each choice of map projection and associated parameters distorts distances at a given point on the globe differently

Geographic grid distance in WRF at a point is given by

$$\Delta x_{geographical} = \Delta x_{nominal}/m$$

where m is a *map scale factor*.


Maximum stable timestep in WRF is determined by geographic grid distance, not nominal (i.e., namelist) grid distance!

Map scale factor is a 2-d field available in the geogrid output files

- Can easily check min/max map scale factor using, e.g., ncview!


Why do map projections matter?

Mercator projection, $\phi_1 = 42.0$, $0.819 \leq m \leq 1.218$



For a nominal 12-km grid, the above projection yields grid distances from 9.9 km to 14.6 km.


Lambert conformal projection, $\phi_1, \phi_2 = 30.0, 47.5$, $0.988 \leq m \leq 1.023$




For a nominal 12-km grid, the above projection yields grid distances from 11.7 to 12.1 km.

Why do map projections matter?

Lesson: After running geogrid.exe, check the MAPFAC_M field in the geogrid output files!



Geogrid: Defining ARW Domains



Geogrid: Defining ARW Domains

- Define the area covered (dimensions and location) by coarse domain using the following:
 - REF_LAT, REF_LON: The (lat,lon) location of a known location in the domain (*by default, the center point of the domain*)
 - DX, DY: Grid distance where map factor = 1
 - For Lambert, Mercator, and polar stereographic: **meters**
 - For (rotated) latitude-longitude: **degrees**
 - E_WE: Number of velocity points in west-east direction
 - E_SN: Number of velocity points in south-north direction

See p. 3-13 and 3-42

Geogrid: Interpolating *Static* Fields


- Given definitions of all computational grids, geogrid interpolates terrestrial, time-invariant fields
 - Topography height
 - Land use categories
 - Soil type (top layer & bottom layer)
 - Annual mean soil temperature
 - Monthly vegetation fraction
 - Monthly surface albedo

Geogrid: Program Output


- The parameters defining each domain, plus interpolated static fields, are written using the WRF I/O API
 - One file per domain for ARW
- Filenames: **geo_em.d0*n*.nc**
(where *n* is the domain ID number)
- Example:
 - [geo_em.d01.nc](#)
 - [geo_em.d02.nc](#) (nest)
 - [geo_em.d03.nc](#) (nest)

Geogrid: Example Output Fields


Land–water
mask




Topography
height



Top-layer
dominant
soil type




Climatological
vegetation
fraction
(January)



The *ungrib* program

External Data
Sources



ungrib: think un+grib

What is a GRIB file, anyway?

- GRIB is a WMO standard file format for storing regularly-distributed (e.g., gridded) fields
 - “General Regularly-distributed Information in Binary”
- Fields within a GRIB file are compressed with a lossy compression
 - Think of truncating numbers to a fixed number of digits
- A record-based format
- Fields in a file are identified only by code numbers
 - These numbers must be referenced against an external table to determine the corresponding field

The *ungrib* program

- Reads GRIB Edition 1 and GRIB Edition 2 files
- Extracts meteorological fields
- If necessary, derives required fields from related ones
 - E.g., Compute RH from T, P, and Q
- Writes requested fields to an *intermediate* file format

How does ungrib know which fields to extract?

Using Vtables (think: Variable tables)

- Vtables are files that give the GRIB codes for fields to be extracted from GRIB input files
- One Vtable for each source of data
- Vtables are provided for: CFSR, ERA-Interim, GFS, NARR, and others

Ungrib: Example Vtable

GRIB1 Param	Level Type	From Level1	To Level2	UNGRIB Name	UNGRIB Units	UNGRIB Description
11	100	*		T	K	Temperature
33	100	*		U	m s ⁻¹	U
34	100	*		V	m s ⁻¹	V
52	100	*		RH	%	Relative Humidity
7	100	*		HGT	m	Height
11	105	2		T	K	Temperature at 2 m
52	105	2		RH	%	Relative Humidity at 2 m
33	105	10		U	m s ⁻¹	U at 10 m
34	105	10		V	m s ⁻¹	V at 10 m
1	1	0		PSFC	Pa	Surface Pressure
130	102	0		PMSL	Pa	Sea-level Pressure
144	112	0	10	SM000010	kg m ⁻³	Soil Moist 0-10 cm below grn layer (Up)
144	112	10	40	SM010040	kg m ⁻³	Soil Moist 10-40 cm below grn layer
144	112	40	100	SM040100	kg m ⁻³	Soil Moist 40-100 cm below grn layer
144	112	100	200	SM100200	kg m ⁻³	Soil Moist 100-200 cm below gr layer
85	112	0	10	ST000010	K	T 0-10 cm below ground layer (Upper)
85	112	10	40	ST010040	K	T 10-40 cm below ground layer (Upper)
85	112	40	100	ST040100	K	T 40-100 cm below ground layer (Upper)
85	112	100	200	ST100200	K	T 100-200 cm below ground layer (Bottom)
91	1	0		SEAICE	propn	Ice flag
81	1	0		LANDSEA	propn	Land/Sea flag (1=land,2=sea in GRIB2)
7	1	0		HGT	m	Terrain field of source analysis
11	1	0		SKINTEMP	K	Skin temperature (can use for SST also)
65	1	0		SNOW	kg m ⁻²	Water equivalent snow depth
223	1	0		CANWAT	kg m ⁻²	Plant Canopy Surface Water
224	1	0		SOILCAT	Tab4.213	Dominant soil type category
225	1	0		VEGCAT	Tab4.212	Dominant land use category

Ungrib: GRIB2 Vtables Entries

metgrid	GRIB2	GRIB2	GRIB2	GRIB2
Description	Discp	Catgy	Param	Level
Temperature	0	0	0	100
U	0	2	2	100
V	0	2	3	100
Relative Humidity	0	1	1	100
Height	0	3	5	100
Temperature at 2 m	0	0	0	103
Relative Humidity at 2 m	0	1	1	103
U at 10 m	0	2	2	103
V at 10 m	0	2	3	103
Surface Pressure	0	3	0	1
Sea-level Pressure	0	3	1	101
Soil Moist 0-10 cm below grn layer (Up)	2	0	192	106
Soil Moist 10-40 cm below grn layer	2	0	192	106
Soil Moist 40-100 cm below grn layer	2	0	192	106
Soil Moist 100-200 cm below gr layer	2	0	192	106
Soil Moist 10-200 cm below gr layer	2	0	192	106
T 0-10 cm below ground layer (Upper)	0	0	0	106
T 10-40 cm below ground layer (Upper)	0	0	0	106
T 40-100 cm below ground layer (Upper)	0	0	0	106
T 100-200 cm below ground layer (Bottom)	0	0	0	106
T 10-200 cm below ground layer (Bottom)	0	0	0	106
Ice flag	0	2	0	1
Land/Sea flag (1=land, 0 or 2=sea)	2	0	0	1
Terrain field of source analysis	2	0	7	1
Skin temperature (can use for SST also)	0	0	0	1
Water equivalent snow depth	0	1	13	1
Dominant soil type cat. (not in GFS file)	2	3	0	1
Dominant land use cat. (not in GFS file)	2	0	198	1

What if a data source has no existing Vtable?

Create a Vtable

- Get a listing of GRIB codes for fields in the source
 - Check documentation from originating center or use utility such as *wgrib*, *g1print*, *g2print*
- Use existing Vtable as a template
- Check documentation in Chapter 3 of the Users' Guide for more information about Vtables

See p. 3-35

Ungrib: Intermediate File Format

- After extracting fields listed in Vtable, ungrib writes those fields to intermediate format
- For meteorological data sets not in GRIB format, the user may write to intermediate format directly
 - Allows WPS to ingest new data sources; basic programming required of user
 - Simple intermediate file format is easily read/written using routines from WPS (`read_met_module.F` and `write_met_module.F`)

See p. 3-33

Ungrib: Program Output

- Output files named *FILE:YYYY-MM-DD_HH*
 - *YYYY* is year of data in the file; *MM* is month; *DD* is day; *HH* is hour
 - All times are UTC
- Example:


FILE:2007-07-24_00

FILE:2007-07-24_06

FILE:2007-07-24_12

The *metgrid* program

External Data
Sources




metgrid: think meteorological

The *metgrid* program

- Horizontally interpolate meteorological data (*extracted by ungrb*) to simulation domains (*defined by geogrid*)
 - Masked interpolation for masked fields
 - *Can process both isobaric and native vertical coordinate data sets*
- Rotate winds to WRF grid
 - i.e., rotate so that U-component is parallel to x -axis, V-component is parallel to y -axis

Metgrid: ARW Grid Staggering

- For ARW, wind U-component interpolated to “u” staggering
- Wind V-component interpolated to “v” staggering
- Other meteorological fields interpolated to “ θ ” staggering by default (*can change this!*)




A single ARW grid cell, with “u”, “v”, and “θ” points labeled.

Metgrid: Masked Interpolation

- *Masked fields* may only have valid data at a subset of grid points
 - E.g., SST field only valid on water points
- When metgrid interpolates masked fields, it must know which points are invalid (masked)
 - Can use separate mask field (e.g., LANDSEA)
 - Can rely on special values (e.g., 1×10^{30}) in field itself to identify masked grid points

Metgrid: Masked Interpolation



● = valid source data
● = masked/invalid data


Suppose we need to interpolate to point X

- Using **red** points as valid data can give a bad interpolated value!
- Masked interpolation only uses valid **blue** points to interpolate to X

Not every interpolation option can handle masked points; we'll address this issue in the advanced WPS lecture

Metgrid: Masked Interpolation

Common fields that require masked interpolation include SST, soil moisture, and soil temperature.




A high-resolution WRF domain centered on Pearl River Estuary.

SST data on a 0.083-degree grid, with missing data (black) over land.


SST data overlaid with land use; blue areas represent WRF water cells that must receive SST values via masked interpolation.

Metgrid: Masked Interpolation

Masked interpolation can also be used for any field, e.g., to improve the resolution of coastlines in the field.



Skin temperature field interpolated from GFS 0.5-deg field with no mask using a sixteen-point interpolator.




Skin temperature field interpolated using masks: GFS water points interpolated to model water points, GFS land points interpolated to model land points.


Metgrid: Wind Vector Rotation

- Input wind fields (U-component + V-component) are either:
 - **Earth-relative:** U-component = westerly component; V-component = southerly component
 - **Relative to source grid:** U-component (V-component) parallel to source model x-axis (y-axis)
- WRF expects wind components to be relative to the simulation grid

Metgrid: Wind Vector Rotation



A wind vector, shown in terms of its U and V components with respect to the source grid.



The same vector, in terms of its U and V components with respect to the WRF simulation grid.

This process may require *two* rotations: one from source grid to earth grid and a second from earth grid to WRF grid

Metgrid: Constant Fields






- For short simulations, some fields may be constant
 - E.g., SST or sea-ice fraction
- Use namelist option `CONSTANTS_NAME` option to specify such fields:
 - `CONSTANTS_NAME = 'SST_FILE:2007-07-24_00'`

Metgrid: Program Output


- For coarse domain, one file per time period
 - In ARW, we also get the first time period for all nested grids
- Files contain static fields from geogrid plus interpolated meteorological fields
- Filenames:

ARW: `met_em.d0n.YYYY-MM-DD_HH:mm:ss.nc`
(where n is the domain ID number)

Metgrid: Example Output




WPS Summary



And finally...

Vertical interpolation to WRF eta levels is performed in the *real* program



Questions?


Extra slides

Why do map projections matter?

Example:

- Nominally 27 km grid
- Lambert conformal projection
- True latitude 1 = 23.14
- True latitude 2 = 23.14



Choosing both true latitudes in the center of the WRF domain leads to maximum map scale factors of 1.0975, corresponding to a *minimum physical grid distance of $27/1.0975 = 24.6 \text{ km}$.*



Above: Contours of map scale factor (white; interval 0.01) with true latitudes (red).


Why do map projections matter?

We can reduce the maximum map scale factor at the expense of grid resolution...




Why do map projections matter?

... but if we insist that the maximum grid distance is at most 27 km, we must reduce the *nominal* grid distance to accommodate the map scale factors!



Above: With a nominal grid distance of 27 km, the map scale factors of 0.924 in the center of the map correspond to a physical distance of 29.2 km.



Above: Reducing the nominal grid distance to 25 km, the map scale factors of 0.924 in the center of the map correspond to a physical distance of 27.06 km.