

Initialization for Idealized Cases

Shu-Hua Chen

University of California, Davis

Bill skamarock
skamaroc@ucar.edu


Color Legend

Directories, Files

Commands, Executions

Special Comments


WRF code



Test Cases for the WRF ARW Model

- 2D flow over a bell-shaped mountain

WRFV2/test/em_hill2d_x




Test Cases for the WRF ARW Model

- 2D flow over a bell-shaped mountain
WRFV2/test/em_hill2d_x
- 2D squall line (x, z ; y, z)
WRFV2/test/em_squall2d_x
WRFV2/test/em_squall2d_y
- 3D quarter-circle shear supercell thunderstorm
WRFV2/test/em_quarter_ss
- 3D baroclinic wave
WRFV2/test/em_b_wave
- 2D gravity current
WRFV2/test/em_grav2d_x


2D Flow Over a Bell-Shaped Mountain

(dx = 2 km, dt = 20 s, T=10 hr)



Run 2D Flow Over a Bell-Shaped Mountain

From *WRFV2* - compile *em_hill2d_x* ;
From *WRFV2/test/em_hill2d_x* - run *ideal.exe*, run *wrf.exe*




Run 2D Flow Over a Bell-Shaped Mountain

From *WRFV2* - compile *em_hill2d_x* ;
From *WRFV2/test/em_hill2d_x* - run *ideal.exe*, run *wrf.exe*

Initialization code is in

WRFV2/dyn_em/module_initialize_hill2d_x.F

The terrain profile is set in the initialization code.



Run 2D Flow Over a Bell-Shaped Mountain

From **WRFV2** - **compile em_hill2d_x** ;
From **WRFV2/test/em_hill2d_x** - run **ideal.exe**, run **wrf.exe**

Initialization code is in

WRFV2/dyn_em/module_initialize_hill2d_x.F

The terrain profile is set in the initialization code.

The thermodynamic sounding and the initial wind field is read from the ascii file

WRFV2/test/em_hill2d_x/input_sounding

The 2D solution is computed by integrating the 3D model with 3 points in periodic direction y; without an initial perturbation in y the solution remains y-independent.

Setting the terrain heights

In **WRFV2/dyn_em/module_initialize_hill2d_x.F**

```

SUBROUTINE init_domain_rk ( grid, &
...
  hm = 100.0      ← mountain height and half-width
  xa = 5.0
...
  icm = ide/2      ← mountain position in domain
                    (central gridpoint in x)
...
  DO j=jts,jte
  DO i=its,ite ! flat surface
    ht(i,j) = 0.
    ht(i,j) = hm/(1.+(float(i-icm)/xa)**2)
    ht(i,j) = hml*exp(-((float(i-icm)/xal)**2)) &
              *(cos(pii*float(i-icm)/xall)**2)
    phb(i,1,j) = g*ht(i,j)
    php(i,1,j) = 0. ← lower boundary condition
    ph0(i,1,j) = phb(i,1,j)
  ENDDO
ENDDO

```

Set height field →

Setting the Initial Condition

In **WRFV2/dyn_em/module_initialize_hill2d_x.F**

```

SUBROUTINE init_domain_rk ( grid, &
...
! get the sounding from the ascii sounding file, first get dry sounding and
! calculate base state
...
write(6,*) ' getting dry sounding for base state '
dry_sounding = .true.
CALL get_sounding( zk, p_in, pd_in, theta, rho, u, v, qv, dry_sounding, &
  nl_max, nl_in, .true.)
...
! calculate full state for each column - this includes moisture.
...
write(6,*) ' getting moist sounding for full state '
dry_sounding = .false.
CALL get_sounding( zk, p_in, pd_in, theta, rho, u, v, qv, dry_sounding, &
  nl_max, nl_in, .false. )
...

```

Base state
Dry sounding


Full state
Moist sounding

Sounding File Format

File: **WRFV2/test/em_quarter_ss/input_sounding**

	surface Pressure (mb)	surface potential Temperature (K)	Surface vapor mixing ratio (g/kg)		
line 1 →	1000.00	300.00	14.00		
each successive line is a point in the sounding	250.00	300.45	14.00	-7.88	-3.58
	750.00	301.25	14.00	-6.94	-0.89
	1250.00	302.47	13.50	-5.17	1.33
	1750.00	303.93	11.10	-2.76	2.84
	2250.00	305.31	9.06	0.01	3.47
	2750.00	306.81	7.36	2.87	3.49
	3250.00	308.46	5.95	5.73	3.49
	3750.00	310.03	4.78	8.58	3.49
	4250.00	311.74	3.82	11.44	3.49
	4750.00	313.48	3.01	14.30	3.49
	height (m)	potential temperature (K)	vapor mixing ratio (g/kg)	U (west-east velocity (m/s))	V (south-north velocity (m/s))

2D squall line simulation



Run 2D squall line simulation

* *squall2d_x* is (x,z), *squall2d_y* is (y,z); both produce the same solution.


From *WRFV2* – compile *em_squall2d_x* ;
 From *WRFV2/test/em_squall2d_x* – run *ideal.exe*, run *wrf.exe*

Initialization code is in
WRFV2/dyn_em/module_initialize_squall2d_x.F
 This code also introduces the initial perturbation.

The thermodynamic sounding and hodograph
 is in the ascii input file
WRFV2/test/em_squall2d_x/input_sounding

3D supercell simulation

Height coordinate model
 ($dx = dy = 2$ km, $dz = 500$ m, $dt = 12$ s, $160 \times 160 \times 20$ km domain)
 Surface temperature, surface winds and cloud field at 2 hours



Run 3D supercell simulation

From *WRFV2* – compile *em_quarter_ss* ;
 From *WRFV2/test/em_quarter_ss* – run *ideal.exe*, run *wrf.exe*

Initialization code is in
WRFV2/dyn_em/module_initialize_quarter_ss.F

The thermodynamic sounding and hodograph is read
 from the ascii input file
WRFV2/test/em_quarter_ss/input_sounding

The initial perturbation (warm bubble) is hardwired
 in the initialization code.

Setting the initial perturbation

In *WRFV2/dyn_em/module_initialize_quarter_ss.F*

```

SUBROUTINE init_domain_rk ( grid, &
...
! thermal perturbation to kick off convection
...
DO J = jts, min(jde-1,jte)
  yrad = dy*float(j-nyc)/10000.
  yrad = 0.
  DO I = its, min(ide-1,ite)
    xrad = dx*float(i-nxc)/10000.
    xrad = 0.
    DO K = 1, kte-1
      ! put in perturbation theta (bubble) and recalc density. note,
      ! the mass in the column is not changing, so when theta changes,
      ! we recompute density and geopotential.

      zrad = 0.5*(ph_1(i,k,j)+ph_1(i,k+1,j) &
        +phb(i,k,j)+phb(i,k+1,j))/g
      zrad = (zrad-1500.)/1500.
      RAD=SQRT(xrad*xrad+yrad*yrad+zrad*zrad)
      IF (RAD <= 1.) THEN
        T_1(i,k,j)=T_1(i,k,j)+delt* $\cos(.5*PI*RAD)**2$ 
        T_2(i,k,j)=T_1(i,k,j)
        qvf = 1. + 1.61*moist_1(i,k,j,P_QV)
        al1(i,k,j) = (r_d/p1000mb)*(T_1(i,k,j)+T0)*qvf* &
          ((p(i,k,j)+pb(i,k,j))/p1000mb)**cvpm)
        al(i,k,j) = al1(i,k,j) - al1(i,k,j)
      ENDIF
    ENDDO
  ENDDO

```

horizontal radius of the perturbation is 10 km, centered at (x,y) gridpoints (nxc, nyc)


vertical radius of the perturbation is 1500 m

maximum amplitude of the perturbation

perturbation added to initial theta field

Moist Baroclinic Wave Simulation

Height coordinate model ($dx = 100$ km, $dz = 250$ m, $dt = 600$ s)
Surface temperature, surface winds, cloud and rain water




Open Channel Baroclinic Wave Simulation

Day 5, $dt = 600$ s, $dx = dy = 100$ km, 14000 x 8000 km

Free Slip
Warm Rain

MRF PBL - land
KF Conv. Param.
Ice Microphysics



Run Moist Baroclinic Wave Simulation

From *WRFV2* – compile *em_b_wave* ;
From *WRFV2/test/em_b_wave* – run *ideal.exe*, run *wrf.exe*

Initialization code is in
WRFV2/dyn_em/module_initialize_b_wave.F

The initial jet (y,z) is read from the binary input file
WRFV2/test/em_b_wave/input_jet

The initial perturbation is hardwired in the initialization code.

Moist Baroclinic Wave Simulation

Default configuration in

WRFV2/test/em_b_wave/namelist.input

runs the dry jet in a periodic channel with dimension (4000 x 8000 x 16 km) (x,y,z).

Turning on any microphysics

(mp_physics > 0 in namelist.input) puts moisture into the basic state.

Switching from periodic to open boundary conditions along with lengthening the channel produces a baroclinic wave train.

The initial jet only works for $dy = 100$ km and 81 grid points in the y (south-north) direction.

Gravity Current Simulation


(Straka et al, IJNMF, 1993)

2D channel (x, z ; 51.2 x 6.4 km)


Initial state: $\theta = 300$ K (neutral) + perturbation (max = 16.2 K)

Eddy viscosity = $75 \text{ m}^2/\text{s}$ (constant)

Initial state, potential temperature (c.i. = 1 K)



Gravity Current Simulation




Gravity Current Simulation

Default case, $dx = 100$ m,
5th order upwind advection,
uses namelist.input.100m

$dx = 200$ m,
5th order upwind advection,
use namelist.input.200m

$dx = 400$ m,
5th order upwind advection,
use namelist.input.400m




Gravity Current Simulation

5th order upwind advection,
use namelist.input.200m
and input_sounding.um=20

use namelist.input.100m
with 2nd order advection
and input_sounding.um=20

use namelist.input.200m
with 2nd order advection
and input_sounding.um=20



Run Gravity Current Simulation

From **WRFV2** – *compile em_grav2d_x* ;
From **WRFV2/test/em_grav2d_x** – run *ideal.exe*, run *wrf.exe*

Initialization code is in

WRFV2/dyn_em/module_initialize_grav2d_x.F

The initial cold bubble is hardwired in the
initialization code.