



WRF: Set up and Run

Set Up and Run WRF (ARW-Ideal and ARW-real)

Wei Wang
NCAR/MMM




WRF System Flowchart



Outline


- Running WRF code
 - Before you run..
 - Running **ARW real-data** case
 - Running **idealized** case
- Basic runtime options for a single domain run (*namelist*)
- Check output
- Simple trouble shooting

This talk is complementary to 'Nesting' talk later.



Before You Run ..


- Check and make sure appropriate executables are created in **WRFV3/main/** directory:
For ARW:
 - **ideal.exe**
 - **real.exe**
 - **wrf.exe**
 - **ndown.exe**
 - **tc.exe**
- If you are running a real-data case, be sure that files from WPS are correctly generated:
 - **met_em.d01.***, for ARW or
- Prepare **namelist.input** for runtime options.



WRF test case directories

You have these choices in **WRFV3/test/**

(made at compile time):



Steps to Run

1. cd to *run/* or one of the *test case* directories
2. Link or copy WPS output files to the directory for real-data cases
3. Edit *namelist.input* file for the appropriate grid and times of the case
4. Run initialization program (*ideal.exe*, *real.exe*)
5. Run model executable, *wrf.exe*



WRFV3/run directory

README.namelist

LANDUSE.TBL
ETAMPNEW_DATA
GENPARM.TBL
RRTM_DATA
RRTMG_SW_DATA
RRTMG_LW_DATA
SOILPARM.TBL
VEGPARM.TBL
URBAN_PARAM.TBL
tr49t67
tr49t85
tr67t85
gribmap.txt
grib2map.tbl

.... (a few more)

*these files are model
physics data files: they are
used to either initialize
physics variables, or make
physics computation more
efficient*




WRFV3/run directory after compile


LANDUSE.TBL
ETAMPNEW_DATA
GENPARM.TBL
RRTM_DATA
RRTMG_SW_DATA
RRTMG_LW_DATA
SOILPARM.TBL
VEGPARM.TBL
URBAN_PARAM.TBL
tr49t67
tr49t85
tr67t85
gribmap.txt
grib2map.tbl
namelist.input -> ../test/em_real/*namelist.input*
real.exe -> ../main/real.exe
wrf.exe -> ../main/wrf.exe
ndown.exe -> ../main/ndown.exe

... (a few more)

*An example after
ARW real case
compile*



Running **ARW** Real-Data Case



Running ARW Real-Data Case

- If you have compiled the *em_real* case, you should have:

real.exe - real data initialization program

wrf.exe - model executable

ndown.exe - program for doing one-way nesting

tc.exe - program for TC bogusing

- These executables are linked to:

WRFV3/run

and

WRFV3/test/*em_real*



➔ One can go to either directory to run.

WRFV3/test/*em_real* directory

```
LANDUSE.TBL -> ../../run/LANDUSE.TBL
ETAMPNEW_DATA -> ../../run/ETAMPNEW_DATA
GENPARM.TBL -> ../../run/GENPARM.TBL
RRTM_DATA -> ../../run/RRTM_DATA
RRTMG_SW_DATA -> ../../run/RRTMG_SW_DATA
RRTMG_LW_DATA -> ../../run/RRTMG_LW_DATA
SOILPARM.TBL -> ../../run/SOILPARM.TBL
VEGPARM.TBL -> ../../run/VEGPARM.TBL
URBAN_PARAM.TBL -> ../../run/URBAN_PARAM.TBL
tr49t67 -> ../../run/tr49t67
tr49t85 -> ../../run/tr49t85
tr67t85 -> ../../run/tr67t85
gribmap.txt -> ../../run/gribmap.txt
grib2map.tbl -> ../../run/grib2map.tbl
namelist.input - require editing
real.exe -> ../../main/real.exe
wrf.exe -> ../../main/wrf.exe
ndown.exe -> ../../main/ndown.exe
... (a few more)
```




Running WRF *ARW* Real-data Cases

- One must successfully run WPS, and create *met_em.** file for more than one time period
- Link or copy WPS output files to the run directory:

```
cd test/em_real
```

```
ln -s ../ ../WPS/met_em.d01.* .
```



Running WRF ARW Real-data Cases

- Edit `namelist.input` file for runtime options (at minimum, one must edit `&time_control` for start, end and integration times, and `&domains` for grid dimensions)
- Run the real-data initialization program:
 `./real.exe`, if compiled serially / SMP, or
 `mpirun -np N ./real.exe`, or
 `mpirun -machinefile file -np N ./real.exe`
 for a MPI job
 where *N* is the number of processors requested, and
 file has a list of CPUs for the MPI job



Running WRF *ARW* Real-data Cases

- Successfully running this program will create model initial and boundary files:

`wrfinput_d01`

`wrfbdy_d01`

*Single time level
data at model's
start time*

*Multiple time level data
at the lateral boundary,
and only for domain 1*



Running WRF **ARW** Real-data Cases

- Run the model executable by typing:

```
./wrf.exe >& wrf.out &
```

or

```
mpirun -np N ./wrf.exe &
```

- Successfully running the model will create a model *history* file:

```
wrfout_d01_2005-08-28_00:00:00
```

And *restart* file if **restart_interval** is set to a time within the range of the forecast time:

```
wrfirst_d01_2008-08-28_12:00:00
```



Running an Idealized Case

ARW only



Running an *Idealized* Case

- If you have compiled an ideal case, you should have:
`ideal.exe` - ideal case initialization program
`wrf.exe` - model executable
 - These executables are linked to:
`WRFV3/run`
and
`WRFV3/test/em_test-case`
- ➔ One can go to either directory to run.



Running an *Idealized* Case

Go to the desired *ideal* test case directory: e.g.

```
cd test/em_quarter_ss
```

If there is '`run_me_first.csh`' in the directory, run it first - this links physics data files to the correct directory:

```
./run_me_first.csh
```



Running an *Idealized* Case

Then run the ideal initialization program:


`./ideal.exe`

The input to this program is typically a sounding file (file named *input_sounding*), or a pre-defined 3D input (e.g. *input_jet* in **em_b_wave** case).

Running *ideal.exe* creates WRF initial condition file:

`wrfinput_d01`

Note that wrfbdy file is not needed for idealized cases.



Running an *Idealized* Case

- To run the model interactively, type
`./wrf.exe >& wrf.out &`
for single processor (serial) or SMP run. Or
`mpirun -np N ./wrf.exe &`
for a MPI run (where *N* is the number of processors requested)
- Successful running of the model executable will create a model history file called `wrfout_d01_<date>`
e.g. `wrfout_d01_0001-01-01_00:00:00`




Running an *Idealized* Case


- Edit `namelist.input` file to change options.
- For your own case, you may provide a different sounding.
- You may also edit `dyn_em/module_initialize_<case>.F` to change other aspects of the initialization.

Note:

- For 2D cases and baroclinic wave case, `ideal.exe` must be run serially
- For all 2D cases, `wrf.exe` must be run serially or with SMP
- For the 1D case, compile and run serially



Basic namelist Options



What is a namelist?

- A Fortran namelist contains a list of *runtime* options for the code to read in during its execution. Use of a namelist allows one to change runtime configuration without the need to recompile the source code.
- Fortran 90 namelist has very specific format, so edit with care:

```
&namelist-record - start  
/                      - end
```

- As a general rule:
Multiple columns: domain dependent
Single column: value valid for all domains



&time_control

```
run_days           = 0,  
run_hours          = 24,  
run_minutes        = 0,  
run_seconds        = 0,  
start_year         = 2000, 2000, 2000,  
start_month        = 01, 01, 01,  
start_day          = 24, 24, 24,  
start_hour         = 12, 12, 12,  
start_minute       = 00, 00, 00,  
start_second       = 00, 00, 00,  
end_year           = 2000, 2000, 2000,  
end_month          = 01, 01, 01,  
end_day            = 25, 25, 25,  
end_hour           = 12, 12, 12,  
end_minute         = 00, 00, 00,  
end_second         = 00, 00, 00,  
interval_seconds   = 21600  
history_interval   = 180, 60, 60  
frame_per_outfile  = 1000, 1000, 1000,  
restart_interval   = 360,
```

domain 1 option

nest options



Notes on `&time_control`

- `run_*` time variables:
 - Model simulation length: `wrf.exe` and domain 1 only
- `start_*` and `end_*` time variables:
 - Program `real` will use WPS output between these times to produce lateral (and lower) boundary file
 - They can also be used to specify the start and end of simulation times for the coarse grid.



Notes on `&time_control`

- *Interval_seconds*:
 - Time interval between WPS output times, and LBC update frequency
- *history_interval*:
 - Time interval in minutes when a history output is written
 - The time stamp in a history file name is the time when the history file is first written, and multiple time periods may be written in one file. e.g. a history file for domain 1 that is first written for 1200 UTC Jan 24 2000 is
`wrfout_d01_2000-01-24_12:00:00`



Notes on `&time_control`

- *frame_per_outfile*:
 - Number of history times written to one file.
- *restart_interval*:
 - Time interval in minutes when a restart file is written.
 - By default, restart file is not written at hour 0.
 - A restart file contains only one time level data, and its valid time is in its file name, e.g. a restart file for domain 1 that is valid for 0000 UTC Jan 25 2000 is

`wrfirst_d01_2000-01-25_00:00:00`



&time_control


```
io_form_history      = 2,  
io_form_restart     = 2,  
io_form_input       = 2,  
io_form_boundary     = 2,  
debug_level         = 0,
```

IO format options:

- = 1, binary
- = 2, **netcdf** (most common)
- = 4, PHDF5
- = 5, Grib 1
- = 10, Grib 2

io_form_restart = 102 :
write output in patch
sizes: fast for large grids
and useful for restart file

Debug print control:
Increasing values give
more prints.



&domains


```
time_step                = 180
time_step_fract_num      = 0,
time_step_fract_den      = 1,
max_dom                  = 1,
e_we                     = 74, 112, 94,
e_sn                     = 61, 97, 91,
e_vert                   = 28, 28, 28,
num_metgrid_levels       = 21
num_metgrid_soil_levels  = 4
dx                       = 30000, 10000, 3333,
dy                       = 30000, 10000, 3333,
eta_levels               = 1.0, 0.996, 0.99, 0.98, ... 0.0
p_top_requested          = 5000,
```

nest
options



Notes on `&domains`

- `time_step, time_step_fract_num, time_step_fract_den`:
 - Time step for model integration in seconds.
 - Fractional time step specified in separate integers of numerator and denominator.
 - ARW: `6xDX`; (DX is grid distance in km)
- `e_we, e_sn, e_vert`:
 - Model grid dimensions (staggered) in X, Y and Z directions.
- `num_metgrid_levels`:
 - Number of *metgrid* (input) data levels.
- `num_metgrid_soil_levels`:
 - Number of soil data levels in the input data
- `dx, dy`:
 - grid distances in meters for ARW



Notes on `&domains`

- *`p_top_requested`*:
 - Pressure value at the model top.
 - Constrained by the available data from WPS.
 - Default is 5000 hPa
- *`eta_levels`*:
 - Specify your own model levels from 1.0 to 0.0.
 - If not specified, program *`real`* will calculate a set of levels for you



Where do I start?


- Always start with a *namelist* template provided in a test case directory, whether it is a ideal case, or real data case.
 - A number of namelist templates are provided in *test/test-case/* directories

For example: in *test/em_real/*, there are
namelist.input.4km ~ 4 km grid size
namelist.input.jun01 ~ 10 km grid size
namelist.input.jan00 ~ 30 km grid size




Where do I start?

- Use document to guide the modification of the namelist values:
 - run/README.namelist
 - User's Guide, Chapter 5 (online version has the latest)
 - Full list of namelists and their default values can be found in Registry files: [Registry.EM](#) (ARW), and registry.io_boilerplate (IO options, shared)




To run a job in a different directory..

- Directories *run/* and *test_<case>/* are convenient places to run, but it does not have to be.
- Copy or link the content of these directories to another directory, including physics data files, wrf input and boundary files and wrf **namelist** and **executables**, and you should be able to run a job anywhere on your system.



Check Output



Output After a Model Run

- Standard out/error files:
`wrf.out`, or `rs1.*` files
- Model history file(s):
`wrfout_d01_<date>`
- Model restart file(s), optional
`wrfirst_d01_<date>`



Output from a multi-processor run

The standard out and error will go to the following files for a MPI run:

```
mpirun -np 4 .wrf.exe ➔
```

```
rs1.out.0000
```

```
rs1.error.0000
```

```
rs1.out.0001
```

```
rs1.error.0001
```


```
rs1.out.0002
```

```
rs1.error.0002
```

```
rs1.out.0003
```

```
rs1.error.0003
```

There is one pair of files for each processor requested



What to Look for in a standard out File?


Check run log file by typing

```
tail wrf.out, or
```

```
tail rsl.out.0000
```

You should see the following if the job is successfully completed:

```
wrf: SUCCESS COMPLETE WRF
```



How to Check Model History File?

- Use **ncdump**:

```
ncdump -v Times wrfout_d01_<date>
```

to check output times. Or

```
ncdump -v U wrfout_d01_<date>
```

to check a particular variable (U)

- Use **ncview** or **ncBrowse** (great tools!)
- Use post-processing tools (see talks later)



What is in a *wrf.out* or *rsl* file?

- A print of namelist options
- Time taken to compute one model step:

```
Timing for main: time 2000-01-24_12:03:00 on domain 1: 3.25000 elapsed seconds.  
Timing for main: time 2000-01-24_12:06:00 on domain 1: 1.50000 elapsed seconds.  
Timing for main: time 2000-01-24_12:09:00 on domain 1: 1.50000 elapsed seconds.  
Timing for main: time 2000-01-24_12:12:00 on domain 1: 1.55000 elapsed seconds.
```

- Time taken to write history and restart file:

```
Timing for Writing wrfout_d01_2000-01-24_18:00:00 for domain 1: 0.14000 elapsed seconds.
```


- Any model error prints: (example from ARW run)

```
5 points exceeded cfl=2 in domain 1 at time 4.200000 MAX AT i,j,k: 123 48 3  
cfl,w,d(eta)= 4.165821
```

→ An indication the model has become numerically unstable



Simple Trouble Shooting



Often-seen runtime problems

- `module_configure: initial_config: error reading namelist: &dynamics`

- > Typos or erroneous namelist variables exist in namelist record &dynamics in *namelist.input* file

- `input_wrf.F: SIZE MISMATCH: namelist ide,jde,num_metgrid_levels= 70 61 27 ; input data ide,jde,num_metgrid_levels= 74 61 27`

- > Grid dimensions in error



Often-seen runtime problems

- Segmentation fault (core dumped)
 - > Often typing ``unlimit'` or ``ulimit -s unlimited'` or equivalent can help when this happens quickly in a run.
- 121 points exceeded cfl=2 in domain 1 at time 4.200000 MAX AT i,j,k: 123 48 3 cfl,w,d(eta)=4.165821
 - > Model becomes unstable due to various reasons. If it happens soon after the start time, check input data, and/or reduce time step.



References

- Information on compiling and running WRF, and a more extensive list of namelist options and their definition / explanations can be found in the ARW [User's Guide, Chapter 5](#)
- Also see '[Nesting Setup and Run](#)' talk.

