


Real Data Initialization

Dave Gill
gill@ucar.edu



Real-Data Init - EM Core

- Necessary steps to build IC/BC
- Files before and after
- Balancing and Initialization
- Program Flow
- Test Case

Necessary Steps to Build IC/BC

- Build real.exe and wrf.exe
- Fix namelist with run-time options
- Link/copy SI output into correct directory
- Run real.exe

Build real.exe and wrf.exe

- Get zip'ed tar file (Unix only) from WRF download (<http://wrf-model.org>) page, select USERS on main page
- Unzip and untar file
- **cd WRFV2**
- **./configure**
- **./compile em_real**

Fix namelist with run-time options

time_control

```
run_days      = 0,  
run_hours     = 12,  
run_minutes   = 0,  
run_seconds   = 0,
```

Controls coarse grid if present, else the end_*
times are used

WRF only

Fix namelist with run-time options

time_control

```
start_year    = 2000, 2000, 2000,  
start_month   = 01,   01,   01,  
start_day     = 24,   24,   24,  
start_hour    = 12,   12,   12,  
end_year      = 2000, 2000, 2000,  
end_month     = 01,   01,   01,  
end_day       = 25,   25,   25,  
end_hour      = 12,   12,   12,
```

Controls start time for all domains, and end of all
domains except coarse (only if run_* is blank does
end_* affect CG)

Real uses first column only

Fix namelist with run-time options

time_control

```
interval_seconds = 21600  
input_from_file  = .t.  ,.f.  ,.f.,  
history_interval = 180,  60,  60,  
frames_per_outfile = 1000, 1000, 1000,
```

Default unit for history interval is minutes

Frames => how many time periods inside each file

Real only uses interval_seconds to find SI files, and
as lateral BC interval

Fix namelist with run-time options

domains

```
time_step      = 180,  
time_step_fract_num = 0,  
time_step_fract_den = 1,  
max_dom        = 1,
```

Default unit for time step seconds (CG only)

Max_dom is total number of domains to be
run during forecast

WRF only

Fix namelist with run-time options

domains

```
s_we      = 1,      1,      1,
e_we      = 74,     112,    94,
s_sn      = 1,      1,      1,
e_sn      = 61,     97,     91,
s_vert    = 1,      1,      1,
e_vert    = 28,     28,     28,
```

“s_” start, always 1, “e_” end, max extent of u,v,w

“we” west-east, left-right, “sn” south-north

“vert” vertical dimension

real uses first column only

Fix namelist with run-time options

domains

```
dx          = 30000, 10000, 3333,
dy          = 30000, 10000, 3333,
```

Dx, dy must be equal


Unit is meters

Real uses first column only

Fix namelist with run-time options

domains

```
grid_id     = 1,      2,      3,
parent_id   = 0,      1,      2,
```




Real uses first column only of grid_id

Fix namelist with run-time options

domains

```
level       = 1,      2,      3,
```



WRF only

Fix namelist with run-time options


domains

```
i_parent_start      = 0,      31,      30,  
j_parent_start      = 0,      17,      30,  
parent_grid_ratio    = 1,      3,      3,  
parent_time_step_ratio = 1,      3,      3,
```


Parent start refers to lower left point in nest
that overlaps with coarse domain

Grid and time ratios not tied to each other
WRF only


Coarse Grid Staggering



Fine Grid Staggering - Mass



Fine Grid Staggering - U



Fix namelist with run-time options **domains**

```
feedback          = 1,  
smooth_option     = 0
```

Feedback options (1 pt, n^2 points) defined in
Registry, on/off switch provided

Smooth options are run-time: 0= no smoothing, 1=
1-2-1 smoother (2 directions), 2= smoother-
desmoother

WRF only

Fix namelist with run-time options **physics**

```
sf_surface_physics = 1,      1,      1,  
num_soil_layers    = 5,
```

Or

```
sf_surface_physics = 2,      2,      2,  
num_soil_layers    = 4,
```

Or

```
sf_surface_physics = 3,      3,      3,  
num_soil_layers    = 6,
```

Real uses first column only

Fix namelist with run-time options **bdy_control**

```
specified         = .true., .false., .false.,  
nested            = .false., .true., .true.,
```

Only the first domain is ever “specified”, all
subsequent nested domains are “nested”

Real uses first column only

Link/copy SI output into correct directory

- `cd ./WRFV2/test/em_real`
- `ln -s \`
 `$MOAD_DATAROOT/siprd/wrf_r* .`
- One SI file required for each of the
 boundary times (as assumed from the
 “interval”)
- Minimum of 2 files required for a real-data
 forecast

Run real.exe

- The real.exe, ndown.exe, wrf.exe are all able to run as distributed-memory parallel
- Serially:
`./real.exe >&! foo.out`
- Parallel:
`mpirun -np n ./real.exe`
`poe ./real.exe`

Run real.exe

- Did it work? Check the stdout file
- Serially:
`tail foo.out`
- Parallel:
`tail rsl.out.0000`
- Look for `"SUCCESS COMPLETE
REAL_EM INIT"`

Files Before and After

- The input files required by real.exe are output from the SI, typically in netCDF
 - The SI output files are usually linked into the real-data directory
 - Times and dimensions are checked
 - Physics options are infrequently impacted by SI output
- ```
ls $MOAD_DATAROOT/siprd/wrf_r*
```

## Files Before and After

- Two output files are generated by the real.exe program: wrfinput\_d01 and wrfbdy\_d01
- Initial time in wrfinput is the initial time of the WRF forecast (from the namelist)  
`ncdump -v Times wrfinput_d01`
- Time periods from wrfbdy file cover forecast period (reported time is at the beginning of the lateral boundary interval)
- Surface physics options are impacted by physics choices selected prior to running real.exe

## Balancing and Initialization

- Mass coordinate, coordinate is reference pressure based, surfaces move up and down in pressure space
- Reference state function of terrain elevation plus several constants
- Pressure => potential temperature => density => geopotential
- All done in  
./WRFV2/dyn\_em/module\_initialize\_real.F

## Reference State

```
p_surf = p00 * EXP (-t00/a + ((t00/a)**2
- 2.*g*ht(i,j)/a/r_d) **0.5)
```

P00 – ref sea level pressure (10<sup>5</sup> Pa)

T00 – ref sea level temperature (290 K)

A – lapse rate (50 K)

Ht – terrain elevation (m)

## Reference State

```
pb(i,k,j) = znu(k)*(p_surf - p_top) + p_top
t_init(i,k,j) = (t00 + A*LOG(pb(i,k,j)/p00))
*(p00/pb(i,k,j))**(r_d/cp) - t0
alb(i,k,j) = (r_d/p1000mb)*(t_init(i,k,j)+t0)
*(pb(i,k,j)/p1000mb)**cvpm
```

Reference 3d pressure, potential temperature, inverse density (defined at mass points, half levels)

## Reference State

```
mub(i,j) = p_surf - p_top
phb(i,k,j) = phb(i,k-1,j) - dnw(k-1)
*mub(i,j)*alb(i,k-1,j)
```

Reference geopotential (full levels, k=1 defined as terrain\*g)

## Balancing

```
p(i,k,j) = p(i,k+1,j) - (mu_2(i,j)
+ qvf1*mub(i,j))/qvf2/rdn(k+1)
alt(i,k,j) = (r_d/p1000mb)*
(t_2(i,k,j)+t0)*qvf*
((p(i,k,j)+pb(i,k,j))/p1000mb)
**cvpm)
al(i,k,j) = alt(i,k,j) - alb(i,k,j)
```

- Integrate perturbation pressure, diagnose perturbation inverse density

## Balancing

```
ph_2(i,k,j) = ph_2(i,k-1,j) - &
dnw(k-1) * (
(mub(i,j)+mu_2(i,j))*al(i,k-1,j) +
mu_2(i,j)*alb(i,k-1,j))
```

- Integrate perturbation geopotential

## Initializing – Met 3D

- All moisture variables initialized automatically (only Qv on lateral boundaries for CG)
- No modifications to input horizontal velocity components (already rotated to the projection)
- Potential temperature has a constant (300 K) removed

## Initializing – Soil/Surface

- Checks for consistent land/soil and various surface fields
- Soil temperatures interpolated from input values to requested levels
- Surface and soil temperatures adjusted due to differences in terrain elevation

## Program Flow

- [Code browser](#)

## Run Through Test Case

- Download
- Build
- Edit namelist
- Copy SI files for input
- Run
- Check if OK

(as close as possible, Klingon for *finis*)



Hegh!