




# Set Up and Run WRF

(ARW-Ideal, ARW-real, and NMM-real)

*Wei Wang*  
*NCAR/NESL/MMM*  
*January 2012*



# WRF System Flowchart



# Outline

- Running WRF code
  - Before you run..
  - Running **idealized** case
  - Running **ARW real-data** case
  - Running **NMM real-data** case
- Basic runtime options for a **single** domain run (*namelist*)
- Check output
- Simple trouble shooting
- Running a nested case: later



# Before You Run ..

---

- Check and make sure appropriate executables are created in **WRFV3/main/** directory:

For ARW:

- **ideal.exe**
- **real.exe**
- **wrf.exe**
- **ndown.exe**
- **tc.exe**


For NMM:

- **real\_nmm.exe**
- **wrf.exe**

- If you are running a real-data case, be sure that files from WPS are correctly generated:

- **met\_em.d01.\***, for ARW or
- **met\_nmm.d01.\*** for NMM

- Prepare **namelist.input** for runtime options.



# WRF test case directories

You have these choices in **WRFV3/test/**

(made at compile time):

**nmn\_real**

**em\_real**

**em\_quarter\_ss**

**em\_b\_wave**

**em\_les**

**em\_tropical\_cyclone**

**em\_heldsuarez**

**em\_hill2d\_x**

**em\_squall2d\_x**

**em\_squall2d\_y**

**em\_grav2d\_x**

**em\_seabreeze2d\_x**

**em\_scm\_xy**

} 3d real-data

} 3d ideal

} 2d ideal

} 1d ideal

**NMM:**

**real\_nmm.exe**


**wrf.exe**

**ARW:**

**real.exe /**

**ideal.exe**

**wrf.exe**



# Steps to Run

1. cd to *run/* or one of the *test case* directories
2. Link or copy WPS output files to the directory for real-data cases
3. Edit *namelist.input* file for the appropriate grid and times of the case
4. Run initialization program (*ideal.exe*, *real.exe*, or *real\_nmm.exe*)
5. Run model executable, *wrf.exe*



# WRFV3/run directory

---

README.namelist

LANDUSE.TBL

GENPARM.TBL

SOILPARM.TBL

VEGPARM.TBL

URBAN\_PARAM.TBL

RRTM\_DATA

RRTMG\_SW\_DATA

RRTMG\_LW\_DATA

CAM\_ABS\_DATA

CAM\_AEROPT\_DATA

ozone.formatted

ozone\_lat.formatted

ozone\_plev.formatted

ETAMPNEW\_DATA

tr49t67

tr49t85


tr67t85

gribmap.txt

grib2map.tbl

(a few more)

*these files are model  
physics data files: they are  
used to either initialize  
physics variables, or make  
physics computation more  
efficient*



# WRFV3/run directory after compile

---

LANDUSE.TBL  
SOILPARM.TBL  
VEGPARM.TBL  
GENPARM.TBL  
URBAN\_PARAM.TBL  
RRTM\_DATA  
RRTMG\_SW\_DATA  
RRTMG\_LW\_DATA  
ETAMPNEW\_DATA  
tr49t67  
tr49t85  
tr67t85

*An example after  
ARW real case  
compile*

...


*namelist.input* -> ../test/em\_real/*namelist.input*

real.exe -> ../main/real.exe

wrf.exe -> ../main/wrf.exe

ndown.exe -> ../main/ndown.exe


... (a few more)





# Running an Idealized Case

## ARW only



# Running an *Idealized* Case

---

- If you have compiled an ideal case, you should have:  
`ideal.exe` - ideal case initialization program  
`wrf.exe` - model executable
  - These executables are linked to:  
`WRFV3/run`  
and  
`WRFV3/test/em_test-case`
- ➔ One can go to either directory to run.



# Running an *Idealized* Case

---

Go to the desired *ideal* test case directory: e.g.

```
cd test/em_quarter_ss
```

If there is '`run_me_first.csh`' in the directory, run it first - this links physics data files to the current directory:

```
./run_me_first.csh
```



# Running an *Idealized* Case

---


Then run the ideal initialization program:

`./ideal.exe`

The input to this program is typically a sounding file (file named *input\_sounding*), or a pre-defined 2D input (e.g. *input\_jet* in *em\_b\_wave* case).

Running *ideal.exe* creates WRF initial condition file:  
*wrfinput\_d01*

*Note that wrfbdy file is not needed for idealized cases.*



# Running an *Idealized* Case

---

- To run the model interactively, type  
`./wrf.exe >& wrf.out &`  
for single processor (serial) or SMP run. Or  
`mpirun -np N ./wrf.exe &`  
for a MPI run (where **N** is the number of processors requested)
- Successful running of the model executable will create a model history file called `wrfout_d01_<date>`  
e.g. `wrfout_d01_0001-01-01_00:00:00`

*Based on start date defined in namelist*




# Running an *Idealized* Case

---


- Edit `namelist.input` file to change options.
- For your own case, you may provide a different sounding.
- You may also edit `dyn_em/module_initialize_<case>.F` to change other aspects of the initialization.

## **Note:**

- For 2D cases and baroclinic wave case, `ideal.exe` must be run serially
- For all 2D cases, `wrf.exe` must be run serially or with SMP
- For the 1D case, compile and run serially



# Running **ARW** Real-Data Case



# Running **ARW** Real-Data Case

---

- If you have compiled the *em\_real* case, you should have:
  - real.exe** - real data initialization program
  - wrf.exe** - model executable
  - ndown.exe** - program for doing one-way nesting
  - tc.exe** - program for TC bogusing
- These executables are linked to:
  - WRFV3/run**
  - and
  - WRFV3/test/*em\_real***




➔ One can go to either directory to run.



# WRFV3/test/em\_real directory

---

```
LANDUSE.TBL -> ../../run/LANDUSE.TBL
GENPARM.TBL -> ../../run/GENPARM.TBL
SOILPARM.TBL -> ../../run/SOILPARM.TBL
VEGPARM.TBL -> ../../run/VEGPARM.TBL
URBAN_PARAM.TBL -> ../../run/URBAN_PARAM.TBL
RRTM_DATA -> ../../run/RRTM_DATA
RRTMG_SW_DATA -> ../../run/RRTMG_SW_DATA
RRTMG_LW_DATA -> ../../run/RRTMG_LW_DATA
ETAMPNEW_DATA -> ../../run/ETAMPNEW_DATA
tr49t67 -> ../../run/tr49t67
tr49t85 -> ../../run/tr49t85
tr67t85 -> ../../run/tr67t85
...
namelist.input - editing required
real.exe -> ../../main/real.exe
wrf.exe -> ../../main/wrf.exe
ndown.exe -> ../../main/ndown.exe
... (a few more)
```




# Running WRF *ARW* Real-data Cases

---

- One must successfully run WPS, and create *met\_em.\** file for more than one time period
- Link or copy WPS output files to the run directory:

```
cd test/em_real
```


```
ln -s ../ ../WPS/met_em.d01.* .
```



# Running WRF **ARW** Real-data Cases

---

- Edit **namelist.input** file for runtime options (at minimum, one must edit **&time\_control** for start, end and integration times, and **&domains** for grid dimensions)
- Run the real-data initialization program:  
    **./real.exe**, if compiled serially / SMP, or  
    **mpirun -np N ./real.exe**, or  
    **mpirun -machinefile file -np N ./real.exe**  
    for a MPI job  
    where **N** is the number of processors requested, and  
    **file** has a list of CPUs for the MPI job



# Running WRF **ARW** Real-data Cases

- Successfully running this program will create model initial and boundary files:


`wrfinput_d01`

`wrfbdy_d01`

*Single time level  
data at model's  
start time*

*N-1 time-level data at  
the lateral boundary,  
and only for domain 1*

*N: the number of time periods processed*



# Running WRF **ARW** Real-data Cases

---

- Run the model executable by typing:

```
./wrf.exe >& wrf.out &
```

or

```
mpirun -np N ./wrf.exe &
```


- Successfully running the model will create a model *history* file:

```
wrfout_d01_2005-08-28_00:00:00
```


*Based on start date defined in namelist*

and a *restart* file if `restart_interval` is set to a time within the range of the forecast time:

```
wrfirst_d01_2008-08-28_12:00:00
```



# Running **NMM** Real-Data Case




# Running **NMM** Real-Data Case

---

- If you have compiled the *nmm\_real*, you should have:  
**real\_nmm.exe** - NMM real date initialization program  
**wrf.exe** - NMM model executable
- These executables are linked to:  
**WRFV3/run**  
and  
**WRFV3/test/*nmm\_real***

➔ One can go to either directory to run.



# WRFV3/test/*nmm\_real* directory

---

```
LANDUSE.TBL -> ../../run/LANDUSE.TBL
GENPARM.TBL -> ../../run/GENPARM.TBL
SOILPARM.TBL -> ../../run/SOILPARM.TBL
VEGPARM.TBL -> ../../run/VEGPARM.TBL
URBAN_PARAM.TBL -> ../../run/URBAN_PARAM.TBL
RRTM_DATA -> ../../run/RRTM_DATA
RRTMG_SW_DATA -> ../../run/RRTMG_SW_DATA
RRTMG_LW_DATA -> ../../run/RRTMG_LW_DATA
ETAMPNEW_DATA -> ../../run/ETAMPNEW_DATA
tr49t67 -> ../../run/tr49t67
tr49t85 -> ../../run/tr49t85
tr67t85 -> ../../run/tr67t85
...
namelist.input - editing required
real_nmm.exe -> ../../main/real_nmm.exe
wrf.exe -> ../../main/wrf.exe
```





# Running WRF **NMM** Real-data Cases


---

- One must successfully run WPS, and create **met\_nmm.\*** file for more than one time period

- Link or copy WPS output files to the run directory:

```
cd test/nmm_real
```

```
ln -s ../ ../WPS/met_nmm.d01.* .
```



# Running WRF **NMM** Real-data Cases

---

- Edit `namelist.input` file for runtime options (at minimum, one must edit `&time_control` for start, end and integration time, and `&domains` for grid dimensions)

- Run the real-data initialization program in MPI:

```
mpirun -np N ./real_nmm.exe
```

Or serially: `./real_nmm.exe >& real_nmm.out`

- Successfully running this program will create model initial and boundary files:

```
wrfinput_d01
```

```
wrfbdy_d01
```



# Running WRF **NMM** Real-data Cases

---

- Run the model executable by typing in MPI:

```
mpirun -np N ./wrf.exe
```

Or serially: **./wrf.exe >& wrf.out**

- Successfully running the model will create a model *history* file:

```
wrfout_d01_2005-08-28_00:00:00
```

and a *restart* file if **restart\_interval** is set to a time within the range of the forecast time:

```
wrfirst_d01_2008-08-28_12:00:00
```



# Basic namelist Options



# What is a namelist?

- A Fortran namelist contains a list of *runtime* options for the code to read in during its execution. Use of a namelist allows one to change runtime configuration without the need to recompile the source code.
- Fortran 90 namelist has very specific format, so edit with care:

```
&namelist-record - start  
/                      - end
```

- As a general rule:  
Multiple columns: domain dependent  
Single column: value valid for all domains




# &time\_control

```
run_days  
run_hours  
run_minutes  
run_seconds  
start_year  
start_month  
start_day  
start_hour  
start_minute  
start_second  
end_year  
end_month  
end_day  
end_hour  
end_minute  
end_second  
interval_seconds  
history_interval  
frame_per_outfile  
restart_interval  
restart
```

```
= 0,  
= 24,  
= 0,  
= 0,  
= 2000, 2000, 2000,  
= 01, 01, 01,  
= 24, 24, 24,  
= 12, 12, 12,  
= 00, 00, 00,  
= 00, 00, 00,  
= 2000, 2000, 2000,  
= 01, 01, 01,  
= 25, 25, 25,  
= 12, 12, 12,  
= 00, 00, 00,  
= 00, 00, 00,  
= 21600  
= 180, 60, 60  
= 1000, 1000, 1000,  
= 360,  
= .true.,
```

domain 1 option

nest options



# Notes on `&time_control`

- `run_*` time variables:
  - Model simulation length: `wrf.exe` and domain 1 only
- `start_*` and `end_*` time variables:
  - Program `real` will use WPS output between these times to produce lateral (and lower) boundary file
  - They can also be used to specify the start and end of simulation times for the coarse grid if `run_*` variables are not set (or set to 0).



# Notes on `&time_control`

- *interval\_seconds*:
  - Time interval between WPS output times, and lateral BC (and lower BC) update frequency
- *history\_interval*:
  - Time interval in minutes when a history output is written
  - The time stamp in a history file name is the time when the history file is first written, and multiple time periods may be written in one file. e.g. a history file for domain 1 that is first written for 1200 UTC Jan 24 2000 is  
`wrfout_d01_2000-01-24_12:00:00`





# Notes on `&time_control`

- *frame\_per\_outfile*:
  - Number of history times written to one file.
- *restart\_interval*:
  - Time interval in minutes when a restart file is written.
  - By default, restart file is not written at hour 0.
  - A restart file contains only one time level data, and its valid time is in its file name, e.g. a restart file for domain 1 that is valid for 0000 UTC Jan 25 2000 is `wrfirst_d01_2000-01-25_00:00:00`
- *restart*:
  - whether this is a restart run



# Notes on *restart*

- What is a *restart* run?
  - A restart run is a continuation of a model run.
- How to do a *restart* run:
  - In the first run, set *restart\_interval* to a value that is within the model integration time.
  - A restart file will be created. e.g.  
`wrfirst_d01_2000-01-25_00:00:00`
- When doing a restart run:
  - Set *restart* = .true.,
  - Set start times to restart times in namelist



# &time\_control

```
io_form_history      = 2,  
io_form_restart     = 2,  
io_form_input       = 2,  
io_form_boundary     = 2,  
debug_level        = 0,
```

## IO format options:

- = 1, binary
- = 2, **netcdf** (most common)
- = 4, PHDF5
- = 5, Grib 1
- =10, Grib 2
- =11, pnetCDF

## For large file:

**io\_form\_restart = 102 :**  
write output in patch  
sizes: fast for large grids  
and useful for restart file


Debug print control:  
Increasing values give  
more prints.



## &domains

```
time_step                = 180
time_step_fract_num      = 0,
time_step_fract_den      = 1,
max_dom                  = 1,
e_we                    = 74, 112, 94,
e_sn                    = 61, 97, 91,
e_vert                  = 28, 28, 28,
num_metgrid_levels       = 21
num_metgrid_soil_levels  = 4
dx                      = 30000, 10000, 3333,
dy                      = 30000, 10000, 3333,
eta_levels               = 1.0, 0.996, 0.99, 0.98, ... 0.0
p_top_requested          = 5000,
```

nest  
options



# Notes on `&domains`

- `time_step, time_step_fract_num, time_step_fract_den`:
  - Time step for model integration in seconds.
  - Fractional time step specified in separate integers of numerator and denominator.
  - ARW: `6xDX`; NMM: `2.25xDX` (DX is grid distance in km)
- `e_we, e_sn, e_vert`:
  - Model grid dimensions (staggered) in X, Y and Z directions.
- `num_metgrid_levels`:
  - Number of *metgrid* (input) data levels.
- `num_metgrid_soil_levels`:
  - Number of soil data levels in the input data

Found by typing `ncdump -h met_*.d01.<date> | more`
- `dx, dy`:
  - grid distances: in meters for ARW; in degrees for NMM.



# Notes on `&domains`

- *`p_top_requested`*:
  - Pressure value at the model top.
  - Constrained by the available data from WPS.
  - Default is 5000 Pa
- *`eta_levels`*:
  - Specify your own model levels from 1.0 to 0.0.
  - If not specified, program *`real`* will calculate a set of levels
- *`ptsgm` (NMM only)*:
  - Pressure level (Pa) at which the WRF-NMM hybrid coordinate transitions from sigma to pressure (default: 42000 Pa)



# Where do I start?

- Always start with a *namelist* template provided in a test case directory, whether it is an ideal case, ARW or NMM real data case.
  - A number of namelist templates are provided in *test/test\_<case>/* directories

For example: in *test/em\_real/*, there are  
namelist.input.4km ~ 4 km grid size  
namelist.input.jun01 ~ 10 km grid size  
namelist.input.jan00 ~ 30 km grid size



# Where do I start?

---

- Use document to guide the modification of the namelist values:
  - `run/README.namelist`
  - `test/em_real/examples.namelist`
  - User's Guide, Chapter 5 (online version has the latest)
  - Full list of namelists and their default values can be found in Registry files: [Registry.EM](#) (ARW), [Registry.NMM](#) and `registry.io_boilerplate` (IO options, shared)





# To run a job in a different directory..

- Directories *run/* and *test\_<case>/* are convenient places to run, but it does not have to be.
- Copy or link the content of these directories to another directory, including physics data files, wrf **input** and **boundary** files, wrf **namelist** and **executables**, and you should be able to run a job anywhere on your system.



# Check Output



# Output After a Model Run

- Standard out/error files:  
`wrf.out`, or `rs1.*` files
- Model history file(s):  
`wrfout_d01_<date>`
- Model restart file(s), optional  
`wrfirst_d01_<date>`



# Output from a multi-processor run

---

The standard out and error will go to the following files for a MPI run:

```
mpirun -np 4 ./wrf.exe ➔
```

```
rs1.out.0000
```

```
rs1.error.0000
```

```
rs1.out.0001
```

```
rs1.error.0001
```

```
rs1.out.0002
```

```
rs1.error.0002
```

```
rs1.out.0003
```

```
rs1.error.0003
```

There is one pair of files for each processor requested



# What to Look for in a standard out File?


---

Check run log file by typing

```
tail wrf.out, or  
tail rsl.out.0000
```

You should see the following if the job is successfully completed:

```
wrf: SUCCESS COMPLETE WRF
```



# How to Check Model History File?

---

- Use **ncdump**:

`ncdump -v Times wrfout_d01_<date>`

to check output times. Or

`ncdump -v U wrfout_d01_<date>`

to check a particular variable (U)

- Use **ncview** or **ncBrowse** (great tools!)
- Use post-processing tools (see talks later)



# What is in a *wrf.out* or *rsl* file?

- A print of namelist options
- Time taken to compute one model step:

```
Timing for main: time 2000-01-24_12:03:00 on domain 1: 3.25000 elapsed seconds.  
Timing for main: time 2000-01-24_12:06:00 on domain 1: 1.50000 elapsed seconds.  
Timing for main: time 2000-01-24_12:09:00 on domain 1: 1.50000 elapsed seconds.  
Timing for main: time 2000-01-24_12:12:00 on domain 1: 1.55000 elapsed seconds.
```

- Time taken to write history and restart file:


```
Timing for Writing wrfout_d01_2000-01-24_18:00:00 for domain 1: 0.14000 elapsed seconds.
```

- Any model error prints: (example from ARW run)


```
5 points exceeded cfl=2 in domain 1 at time 4.200000 MAX AT i,j,k: 123 48 3  
cfl,w,d(eta)= 4.165821
```



An indication the model has become numerically unstable



# Simple Trouble Shooting





# Often-seen runtime problems


---

- `module_configure: initial_config: error reading namelist: &dynamics`

> Typos or erroneous namelist variables exist in namelist record &dynamics in *namelist.input* file

- `input_wrf.F: SIZE MISMATCH: namelist ide,jde,num_metgrid_levels= 70 61 27 ; input data ide,jde,num_metgrid_levels= 74 61 27`

> Grid dimensions in error



# Often-seen runtime problems

---

- **Segmentation fault** (core dumped)
  - Often typing `'unlimit'` or `'ulimit -s unlimited'` or equivalent can help when this happens quickly in a run.
- If you do: `grep cfl rsl.error.*` and see  
121 points **exceeded cfl=2** in domain 1 at time  
4.200000 MAX AT i,j,k: 123 48 3 cfl,w,d(eta)=  
4.165821
  - Model becomes unstable due to various reasons. If it happens soon after the start time, check input data, and/or reduce time step.



# References

---

- Information on compiling and running WRF, and a more extensive list of namelist options and their definition / explanations can be found in the ARW and NMM [User's Guide, Chapter 5](#)
- Also see '[Nesting Setup and Run](#)' and '[Other Runtime Options](#)' talks.

