

Real program in a nutshell

- Function
- Standard input variables
- Base State
- Standard generated output
- Vertical interpolation
- Soil level interpolation
- Nested processing

- The WRF model pre-processor is *real.exe*
- The real.exe program is available *serial* or *DM parallel* (primarily for aggregate memory purposes, as opposed to timing performance)
- This program is automatically generated when the model is built and the requested use is for a real data case
- The real.exe program takes data *from WPS* and transform the data *for WRF*
- Similar to the ARW idealized data pre-processor, real.exe is tightly coupled to the WRF model through the *Registry*

- *3D forecast* or simulation
- *Meteorological input* data that primarily originated from a previous forecast or analysis, probably via the WPS package
- Anticipated *utilization of physics* packages for microphysics, surface conditions, radiation, convection, and boundary layer (maybe usage of nudging capabilities)

- A non-Cartesian *projected domain*
 - Lambert conformal, Mercator, polar stereographic, rotated latitude/longitude (global or regional)
- Selection of *realistic static fields* of topography, land use, vegetation, and soil category data
- Requirement of *time dependent* lateral boundary conditions for a regional forecast

- Generation of *diagnostics* necessary for assumed WRF model input
- Input field *adjustment* for consistency of static and time dependent fields (land mask with soil temperature, etc.)
- ARW: computation of *reference* and *perturbation* fields
- Generation of *initial* state for each of the requested domains
- Creation of a *lateral boundary file* for the most coarse domain
- *Vertical interpolation* for 3d meteorological fields and for sub-surface soil data

Standard Input Variables

- The metgrid program typically provides meteorological data to the real program.
- Coordinate:
 - The real program is able to input and correctly process any strictly monotonically oriented vertical coordinate
 - Isobaric: OK
 - Sigma: OK
 - Hybrid: OK

Standard Input Variables

- The metgrid program typically provides meteorological data to the real program.
- Mandatory:
 - 3d and surface: horizontal winds, temperature, relative humidity, geopotential height
 - 3d soil: soil temperature
 - 2d fields: surface pressure, sea-level pressure, land mask
- Optional (but desirable):
 - 3d soil: soil moisture
 - 2d fields: topography elevation of input data, SST, sea-ice, skin temperature

Base State

- Several of the mass-point fields are separated into a timeindependent base state (also called a reference state) and a perturbation from the base state
- The base state fields are only functions of the topography and a few user-selectable constants
- If the topography changes, such as with a moving nest, the base state fields are modified
- Feedback for 2-way nesting also impacts base state fields through topographic averaging
- No base state computations are required prior to the real program

Standard Generated Output

- For regional forecasts, the real program generates both an both an initial (*wrfinput_d01*) and a lateral boundary (*wrfbdy_d01*)
- The boundary file is not required for global forecasts with ARW
- The initial condition file contains a single time period of data
- These files contain data used directly by the WRF model
- The initial condition file may be ingested by the WRFDA code (referred to as a *cold-start*)
- If *n* times were processed with WPS and real, the lateral boundary file contains *n*-1 time slices

Lateral Boundary Condition Times



Lateral Boundary Condition Times



Real-Data Lateral Boundary Condition: Location of Specified and Relaxation Zones



South

- A number of vertical interpolation options are available to users
- The options can have a significant impact on the initial conditions passed to the model
- More information is contained in the info file *README.namelist* in the *run* directory
- Options are located in the *&domains* namelist record of *namelist.input*

Make sure input data is vertically ordered as expected Input 3-D pressure and T, topo, Z, moisture used to compute total surface pressure

- Compute target vertical coordinate using normalized dry column pressure pressure
- User specifies the selected h surfaces in the namelist (or can be computed)
- Vertically interpolate input fields in pressure to the h surfaces in dry pressure: default all variables log

- Select reasonable h levels, or let the real program do it for you
- Verify that the "thicknesses" are acceptable, generally about the same value in the free-atmosphere and less than 1000 m
- It is SAFEST to NOT initially choose h values
 - Initially, select the number of h levels
 - Plot profiles of the resultant heights
 - Adjust the h levels accordingly
- A few namelist options, the terrain elevation, and eta levels completely define the model coordinate for the WRF code

• Adjusted with a few parameters:

&domains
e_vert = 50, 50, 50
p_top_requested = 1000,
&dynamics
base_temp = 290.
iso temp = 200

Vertical cross sections of model height field, with 50 vertical levels and ptop = 10 hPa, above the PBL.

Uniform layers

Exaggerated Stretching

720-820 m



Physical Parameterization Settings

- The real program and the WRF model are tightly coupled
- Most physical parameterization settings in the namlist.input are IGNORED by real
- EXCEPT
 - sf_surface_physics
 - Land surface model (processes soil temperature and soil moisture)
 - Different schemes in WRF use differing numbers of layers
 - The layers are defined in real from the metgrid output

- The WRF model supports several Land Surface schemes:
 - sf_surface_physics = 1, Slab scheme
 - 5 layers
 - Defined with thicknesses: 1, 2, 4, 8, 16 cm



- The WRF model supports several Land Surface schemes:
 - sf_surface_physics = 2, Unified Noah scheme
 - 4 layers
 - Defined with layers: 0-10, 10-40, 40-100, 100-200 cm



- The WRF model supports several Land Surface schemes:
 - sf_surface_physics = 3, RUC scheme
 - 6 levels
 - Defined at levels: 0, 5, 20, 40, 160, 300 cm



- The WRF model supports several Land Surface schemes:
 - sf_surface_physics = 7, PX scheme
 - 2 layers
 - Defined with layers: 0-1, 1-100 cm



Nested Processing

- May read multiple domain input files from metgrid
- Requires only the initial time for the fine domains, unless doing nudging or SST update
- No horizontal interpolation from parent to child
- No consistency checks between domains (handled in the feedback step for the WRF model)
- A *wrfinput_d0x* file is created for each processed input domain
- A lateral boundary file is created only for the most coarse domain

Real program in a nutshell

- Function
- Required input variables
- Base State
- Standard generated output
- Vertical interpolation
- Soil level interpolation
- Nested processing