Initialization for Idealized Cases

Why do we provide idealized cases?


1. The cases provide simple tests of the dynamics solver for a broad range of space and time scale:

LES - Δx meters, Δt < second;

Baroclinic waves - Δx 100 km, Δt = 10 minutes.

- 2. The test cases reproduce known solutions (analytic, converged, or otherwise).
- 3. The cases provide a starting point for other idealized experiments.
- 4. They can be used to test physics development.
- 5. These tests are the easiest way to test the solver.


Idealized Cases: Introduction



WRF ARW Tech Note

A Description of the Advanced Research WRF Version 3 http://www.mmm.ucar.edu/wrf/users/pub-doc.html

WRF ARW code



Idealized Cases: Introduction

Idealized Test Cases for the WRF ARW Model V3.7


- 2D flow over a bell-shaped mountain WRFV3/test/em_hill2d_x
- 2D squall line (x, z; y, z) WRFV3/test/em_squall2d_x, em_squall2d_y
- 2D gravity current WRFV3/test/em_grav2d_x
- 2D sea-breeze case *WRFV3/test/em_seabreeze2d_x*
- 3D large-eddy simulation case *WRFV3/test/em les*
- 3D quarter-circle shear supercell thunderstorm WRFV3/test/em quarter ss
- 3D tropical cyclone *WRFV3/test/em_tropical_cyclone*
- 3D baroclinic wave in a channel *WRFV3/test/em_b_wave*
- 3D global: Held-Suarez case *WRFV3/test/em_heldsuarez*
- 1D single column test configuration *WRFV3/test/em_scm_xy*
- 3D fire model test cases WRFV3/test/em fire
- 3D convective radiative equilibrium test *WRFV3/test/em_convrad*

Running a test case: *em_hill2d_x* example

2D Flow Over a Bell-Shaped Mountain

Initialization module: dyn_em/module_initialize_hill2d_x.F

Case directory: test/em_hill2d_x



From the WRFV3 main directory:

- > configure (choose the *no nesting* option)
- > compile em_hill2d_x


Move to the test directory:

- > cd test/em hill2d x
- > ideal.exe (this produces the ARW initial conditions)
- > wrf.exe (executes ARW)

Finish by plotting output using scripts downloaded from the ARW website (wrf_Hill2d.ncl)

$$(dx = 2km, dt=20s, T=10 h, wrf_Hill2d.ncl)$$

WRF HILL2x Valid: 0001-01-01_10:00:00



What happens during the initialization

- Initialization code: WRFV3/dyn_em/module_initialize_hill2d_x.F
- A single sounding (z, θ, Q_v, u and v) is read in from WRFV3/test/em_hill2d_x/input_sounding
- Sounding is interpolated to the ARW grid, equation of state and hydrostatic balance used to compute the full thermodynamics state. Nonlinearities require that this process be iterative.
- Wind fields are interplolated to model η levels.

Model levels are set within the initialization: code in initialization exist to produce a stretched η coordinate (close to equally spaced z), or equally spaced η coordinate.

3D meshes are always used, even in 2D (x,z; y,z) cases. The third dimension contains only 5 planes, the boundary conditions in that dimension are periodic, and the solutions on the planes are identical in the initial state and remain so during the integration.

Setting the terrain heights

In WRFV3/dyn_em/module_initialize_hill2d_x.F

```
SUBROUTINE init domain rk (grid, &
              hm = 100.
                                 mountain height and half-width
              xa = 5.0
                                 mountain position in domain
              icm = ide/2
                                 (center gridpoint in x)
             DO j=jts,jte
Set height
             DO i=its,ite ! flat surface
field -
            → grid%ht(i,j) = hm/(1.+(float(i-icm)/xa)**2)
               grid%phb(i,1,j) = g*grid%ht(i,j)
               grid%php(i,1,j) = 0. lower boundary condition
               grid%ph0(i,1,j) = grid%phb(i,1,j)
             ENDDO
             ENDDO
```

Sounding File Format


File: WRFV3/test/em_quarter_ss/input_sounding

each successive line is a point in the sounding	surface Pressure (mb) 1000.00 250.00 750.00 1250.00 1750.00 2250.00 2750.00 3250.00 3750.00 4250.00 4750.00	surface potential Temperature (K) 300.00 300.45 301.25 302.47 303.93 305.31 306.81 306.81 308.46 310.03 311.74 313.48	surface vapor mixing ratio (g/kg) 14.00 14.00 14.00 13.50 11.10 9.06 7.36 5.95 4.78 3.82 3.01	-7.88 -6.94 -5.17 -2.76 0.01 2.87 5.73 8.58 11.44 14.30	-3.58 -0.89 1.33 2.84 3.47 3.49 3.49 3.49 3.49
	height (m)	potential temperature (K)	vapor mixing ratio (g/kg)	U (west-east) velocity (m/s)	V (south-north) velocity (m/s)

Idealized Cases: 2d squall line

Squall-Line Simulations, T = 3600 s

 $dx = dz = 250 \text{ m}, \ v = 300 \text{ m}^2/\text{s}$



Idealized Cases: 2d squall line

squall2d_x is (x,z), squall2d_y is (y,z); both produce the same solution.

Initialization codes are in

WRFV3/dyn_em/module_initialize_squall2d_x.F WRFV3/dyn_em/module_initialize_squall2d_y.F This code also introduces the initial perturbation.


The thermodynamic soundings and hodographs are in the ascii input files

WRFV3/test/em_squall2d_x/input_sounding
WRFV3/test/em_squall2d_y/input_sounding

(Straka et al, IJNMF, 1993)

2D channel (x , z ; 51.2 x 6.4 km) Initial state: theta = 300 K (neutral) + perturbation (max = 16.2 K) Eddy viscosity = 75 m**2/s**2 (constant)


Initial state, potential temperature (c.i. = 1 K)



Default case, dx = 100 m, 5th order upwind advection, uses namelist.input.100m

dx = 200 m, 5th order upwind advection, use namelist.input.200m


dx = 400 m, 5th order upwind advection, use namelist.input.400m




5th order upwind advection, use namelist.input.200m and input_sounding.um=20

use namelist.input.100m with 2nd order advection and input_sounding.um=20

use namelist.input.200m with 2nd order advection and input sounding.um=20





Initialization code is in WRFV3/dyn_em/module_initialize_grav2d_x.F

The initial cold bubble is hardwired in the initialization code.

Idealized Cases: 2d sea breeze

Initialization code is in WRFV3/dyn_em/module_initialize_seabreeze2d_x.F

Test case directory is in WRFV3/test/em_seabreeze2d_x


The initial state has no wind, and is perturbed by small random temperature changes

An example to show how to set surface parameters so that one may use full surface physics

Idealized Cases: 3d supercell thunderstorm

Height coordinate model

(dx = dy = 2 km, dz = 500 m, dt = 12 s, 160 x 160 x 20 km domain)Surface temperature, surface winds and cloud field at 2 hours



Idealized Cases: 3d supercell thunderstorm

Initialization code is in WRFV3/dyn_em/module_initialize_quarter_ss.F

The initial perturbation (warm bubble) is hardwired in the initialization code.

Idealized Cases: 3d Large Eddy Simulation (LES)

Initialization code is in WRFV3/dyn_em/module_initialize_les.F


Test case directory is in WRFV3/test/em_les

The default case is a large-eddy simulation of free convective boundary layer with no winds. The turbulence of the free CBL is driven and maintained by namelist-specified surface heat flux.

An initial sounding with mean winds is also provided.

Reference: Moeng et al. 2007 MWR

Idealized Cases: 3d Large Eddy Simulation (LES)



Idealized Cases: 3d tropical cyclone

Default vortex:


- weak (12.9 m/s) axisymmetric analytic vortex (Rotunno and Emanuel, 1987, JAS)
- placed in center of domain
- in "module_initialize_tropical_cyclone.F" users can modify initial size and intensity (see parameters r0, rmax, vmax, zdd)

Default environment:

- mean hurricane sounding from Jordan (1958, J. Meteor.)
- SST = 28 degrees C
- $f = 5e-5 s^{-1}$ (20 degrees North)


Default domain:

- 3000 km x 3000 km x 25 km domain
- default dx,dy is only 15 km: useful for quick tests of new code (i.e., new physics schemes); research-quality studies should use smaller dx,dy



colors = relative humidity (%) contours = azimuthal velocity (m/s)


Idealized Cases: 3d tropical cyclone




colors = 10-m windspeed (m/s) contours = reflectivity (every 10 dBZ)

Idealized Cases: baroclinic wave in a channel

Height coordinate model (dx = 100 km, dz = 250 m, dt = 600 s) Surface temperature, surface winds, cloud and rain water





Idealized Cases: baroclinic wave in a channel

Initialization code is in WRFV3/dyn_em/module_initialize_b_wave.F

The initial jet (y,z) is read from the binary input file WRFV3/test/em_b_wave/input_jet

The initial perturbation is hardwired in the initialization code.

Idealized Cases: baroclinic wave in a channel

Default configuration in WRFV3/test/em_b_wave/namelist.input runs the dry jet in a periodic channel with dimension (4000 x 8000 x 16 km) (x,y,z).

Turning on any microphysics (mp_physics > 0 in namelist.input) puts moisture into the model state.

The initial jet only works for dy = 100 km and 81 grid points in the y (south-north) direction.

Idealized Cases: Global ARW – Held_Suarez test case

Held-Suarez Case

Initialization code is in WRFV3/dyn_em/module_initialize_heldsuarez.F


The initial model state is an isothermal atmosphere on flat earth with no winds, and random temperature perturbation

Test case directory is in WRFV3/test/em_heldsuarez

If you really want to use a global model, then use...

Idealized Cases: Global ARW – Held_Suarez test case





- Global, nonhydrostatic, C-grid Voronoi mesh
- Numerics similar to WRF; WRF-NRCM physics
- No pole problems
- Variable-resolution mesh no nested BC problems

Available at: http://mpas-dev.github.io/









Idealized Cases: More information

Descriptions:

WRFV3/README_test_cases
WRFV3/test/em_*/README

