


Real

Description of General Functions

Dave Gill
gill@ucar.edu



Real program in a nutshell

- Function
- Standard input variables
- Base State
- Standard generated output
- Vertical interpolation
- Soil level interpolation
- Nested processing

Function

- The WRF model pre-processor is *real.exe*
- The real.exe program is available *serial* or *DM parallel* (primarily for aggregate memory purposes, as opposed to timing performance)
- This program is automatically generated when the model is built and the requested use is for a real data case
- The real.exe program takes data *from WPS* and transform the data *for WRF*
- Similar to the ARW idealized data pre-processor, real.exe is tightly coupled to the WRF model through the *Registry*

Function

- *3D forecast* or simulation
- *Meteorological input* data that primarily originated from a previous forecast or analysis, probably via the WPS package
- Anticipated *utilization of physics* packages for microphysics, surface conditions, radiation, convection, and boundary layer (maybe usage of nudging capabilities)

Function

- A non-Cartesian *projected domain*
 - Lambert conformal, Mercator, polar stereographic, rotated latitude/longitude (global or regional)
- Selection of *realistic static fields* of topography, land use, vegetation, and soil category data
- Requirement of *time dependent* lateral boundary conditions for a regional forecast

Function

- Generation of *diagnostics* necessary for assumed WRF model input
- Input field *adjustment* for consistency of static and time dependent fields (land mask with soil temperature, etc.)
- ARW: computation of *reference* and *perturbation* fields
- Generation of *initial* state for each of the requested domains
- Creation of a *lateral boundary file* for the most coarse domain
- *Vertical interpolation* for 3d meteorological fields and for sub-surface soil data

Standard Input Variables

- The metgrid program typically provides meteorological data to the real program.
- **Coordinate:**
 - The real program is able to input and correctly process any *strictly monotonically oriented* vertical coordinate
 - Isobaric: OK
 - Sigma: OK
 - Hybrid: OK

Standard Input Variables

- The metgrid program typically provides meteorological data to the real program.
- **Mandatory:**
 - 3d and surface: horizontal winds, temperature, relative humidity, geopotential height
 - 3d soil: soil temperature
 - 2d fields: surface pressure, sea-level pressure, land mask
- **Optional** (but desirable):
 - 3d soil: soil moisture
 - 2d fields: topography elevation of input data, SST, sea-ice, skin temperature


Base State

- Several of the mass-point fields are *separated* into a time-independent *base state* (also called a reference state) and a *perturbation* from the base state
- The base state fields are only functions of the *topography* and a few user-selectable constants
- If the *topography changes*, such as with a moving nest, the base state fields are modified
- *Feedback* for 2-way nesting also impacts base state fields through topographic averaging – *inside of the WRF model*
- No base state computations are required *prior to the real program*


Standard Generated Output

- For regional forecasts, the real program generates both an initial (*wrfinput_d01*) and a lateral boundary (*wrfbdy_d01*)
- The boundary file is not required for *global forecasts* with ARW
- The *initial condition* file contains a *single time period* of data
- These files contain data used directly by the WRF model
- The initial condition file may be ingested by the *WRFDA* code (referred to as a *cold-start*)
- If *n* times were processed with WPS and real, the lateral boundary file contains *n-1* time slices

Lateral Boundary Condition Times



Real-Data Lateral Boundary Condition: Location of Specified and Relaxation Zones



Vertical Interpolation

- A number of vertical interpolation options are available to users
- The options can have a significant impact on the initial conditions passed to the model
- More information is contained in the info file *README.namelist* in the *run* directory
- Options are located in the *&domains* namelist record of *namelist.input*

Vertical Interpolation

Make sure input data is vertically *ordered* as expected

Input 3-D pressure and T, topo, Z, moisture used to
compute total *surface pressure*

Compute target *vertical coordinate* using normalized dry
column pressure pressure

The *η surfaces* may be computed or selected

Vertically interpolate input fields in pressure to the η
surfaces in dry pressure: default all variables linear in
 $\log(\text{pressure})$

Vertical Interpolation

- Select reasonable η levels, or let the real program do it for you
- Verify that the *“thicknesses” are acceptable*, generally about the same value in the free-atmosphere and less than 1000 m
- It is *SAFEST to NOT initially choose η values*
 - Initially, *select the number* of η levels
 - *Plot profiles* of the resultant heights
 - *Adjust the η levels* accordingly
- A few namelist options, the terrain elevation, and eta levels completely define the model coordinate for the WRF code

Vertical Interpolation

- The *η surfaces* are computed with a few NML parameters:

```
&domains  
e_vert           = 50,      50,      50  
p_top_requested  = 1000,
```

```
&dynamics  
base_temp        = 290.  
iso_temp         = 200
```



Vertical Interpolation

Vertical cross sections of model height field, with 50 vertical levels and $p_{top} = 10$ hPa, above the PBL.

Uniform layers

Exaggerated Stretching

720-820 m













Physical Parameterization Settings

- The real program and the WRF model are tightly coupled
- Most physical parameterization settings in the namlist.input are IGNORED by real
- EXCEPT
 - *sf_surface_physics*
 - Land surface model (processes soil temperature and soil moisture)
 - Different schemes in WRF use *differing numbers of layers*
 - The layers are defined in real from the metgrid output











Soil Level Interpolation

- The WRF model supports several Land Surface schemes:
 - `sf_surface_physics = 1`, Slab scheme
 - 5 layers
 - Defined with thicknesses: 1, 2, 4, 8, 16 cm

Noah		RUC	
Layers	Mid point		Levels
	000 – 010 cm -- 005 cm		000 cm
	010 – 040 cm -- 025 cm		005 cm
	040 – 100 cm -- 070 cm		020 cm
	100 – 200 cm – 150 cm		040 cm
			160 cm
			300 cm











Soil Level Interpolation

- The WRF model supports several Land Surface schemes:
 - `sf_surface_physics = 2`, Unified Noah scheme
 - 4 layers
 - Defined with layers: 0-10, 10-40, 40-100, 100-200 cm

Noah		RUC	
Layers	Mid point		Levels
	000 – 010 cm -- 005 cm		000 cm
	010 – 040 cm -- 025 cm		005 cm
	040 – 100 cm -- 070 cm		020 cm
	100 – 200 cm -- 150 cm		040 cm
			160 cm
			300 cm











Soil Level Interpolation

- The WRF model supports several Land Surface schemes:
 - `sf_surface_physics = 3`, RUC scheme
 - 6 levels
 - Defined at levels: 0, 5, 20, 40, 160, 300 cm

Noah		RUC	
Layers	Mid point		Levels
	000 – 010 cm -- 005 cm		000 cm
	010 – 040 cm -- 025 cm		005 cm
	040 – 100 cm -- 070 cm		020 cm
	100 – 200 cm -- 150 cm		040 cm
			160 cm
			300 cm

Soil Level Interpolation

- The WRF model supports several Land Surface schemes:
 - `sf_surface_physics = 7`, PX scheme
 - 2 layers
 - Defined with layers: 0-1, 1-100 cm

Noah		RUC	
Layers	Mid point		Levels
	000 – 010 cm -- 005 cm		000 cm
	010 – 040 cm -- 025 cm		005 cm
	040 – 100 cm -- 070 cm		020 cm
	100 – 200 cm – 150 cm		040 cm
			160 cm
			300 cm

Nested Processing

- May read *multiple domain input files* from metgrid
- Requires only the *initial time for the fine domains*, unless doing nudging or SST update
- *No horizontal interpolation from parent to child*
- *No consistency checks* between domains (handled in the feedback step for the WRF model)
- A *wrfinput_d0x* file is created for each processed input domain
- A *lateral boundary file* is created only for the *most coarse* domain

Real program in a nutshell

- Function
- Standard input variables
- Base State
- Standard generated output
- Vertical interpolation
- Soil level interpolation
- Nested processing