


Set Up and Run WRF (*real* and *ideal* data)

Wei Wang
July 2019



This material is based upon work supported by the National Center for Atmospheric Research, which is a major facility sponsored by the National Science Foundation under Cooperative Agreement No. 1852977.

WRF System Flowchart



Outline

- Running WRF code
 - Things to check before you run..
 - Running *real-data* case
 - Running *idealized* case
- Basic runtime options for a *single* domain run (*namelist*)
- Check output
- Simple trouble shooting
- Running a nested case: later



Before You Run ..

- Top directory is now **WRF/**
- Make sure appropriate executables are created in **WRF/main/** directory:
 - **ideal.exe** – executable to create idealized IC
 - **real.exe** – executable to create IC/BC
 - **wrf.exe** – executable for model integration
 - **ndown.exe** – utility
 - **tc.exe** – utility routine for TC bogusing
- If you are working with real data, be sure that files for **a few time periods** from WPS are correctly generated:
 - **met_em.d01.***



WRF test case directories

You have these choices in **WRF/test/**

(choices made at compile time. E.g. *compile em_real*):

```
em_real      } 3-dimensional real-data – real.exe
em_quarter_ss
em_b_wave
em_les
em_tropical_cyclone
em_heldsuarez
em_hill2d_x
em_squall2d_x
em_squall2d_y
em_grav2d_x
em_seabreeze2d_x
em_scm_xy    } 1d ideal
```

3d ideal

2d ideal

1d ideal

ideal.exe



Steps to Run

1. cd to *run/* or one of the *test case* directories
2. Move or link WPS output files to the directory for real-data cases
3. Edit *namelist.input* file for the appropriate grid dimensions and times of the case
4. Run a initialization program (*ideal.exe* or *real.exe*)
5. Run model executable, *wrf.exe*



WRF/run directory

```
README.namelist } description of namelists
LANDUSE.TBL
GENPARM.TBL
SOILPARM.TBL
VEGPARM.TBL
URBPARM.TBL
RRTM_DATA
RRTMG_SW_DATA
RRTMG_LW_DATA
CAM_ABS_DATA
CAM_AEROPT_DATA
ozone.formatted
ozone_lat.formatted
ozone_plev.formatted
aerosol.formatted
aerosol_lat.formatted
aerosol_lon.formatted
aerosol_plev.formatted
gribmap.txt
grib2map.tbl
.... (a total of 60 files)
```

These are model physics data files: they are used to either initialize physics variables, or make physics computation faster

** Some of these files are text files, hence editable*

for grib IO



WRF/run directory after compile

```
LANDUSE.TBL
SOILPARM.TBL
VEGPARM.TBL
GENPARM.TBL
URBPARM.TBL
RRTM_DATA
RRTMG_SW_DATA
RRTMG_LW_DATA
ozone.formatted
ozone_lat.formatted
ozone_plev.formatted
...
namelist.input - copied from ../test/em_real/namelist.input
real.exe -> ../main/real.exe
wrf.exe -> ../main/wrf.exe
ndown.exe -> ../main/ndown.exe
.... (a few more)
```

An example after em_real case compile



Running a Real-Data Case



9

Mesoscale & Microscale Meteorological Laboratory / NCAR

Running a Real-Data Case

- If you have compiled the *em_real* case, you should have:
 - real.exe* - real data initialization program
 - wrf.exe* - model executable
 - ndown.exe* - program for doing one-way nesting
 - tc.exe* - program for TC bogusing
- These executables are linked to:
 - WRF/run
 - and
 - WRF/test/*em_real*



➔ One can go to either directory to run.

Mesoscale & Microscale Meteorological Laboratory / NCAR 10

WRF/test/*em_real* directory

```
LANDUSE.TBL -> ../../run/LANDUSE.TBL
GENPARM.TBL -> ../../run/GENPARM.TBL
SOILPARM.TBL -> ../../run/SOILPARM.TBL
VEGPARM.TBL -> ../../run/VEGPARM.TBL
URBPARM.TBL -> ../../run/URBPARM.TBL
RRTM_DATA -> ../../run/RRTM_DATA
RRTMG_SW_DATA -> ../../run/RRTMG_SW_DATA
RRTMG_LW_DATA -> ../../run/RRTMG_LW_DATA
ozone.formatted -> ../../run/ozone.formatted
ozone_lat.formatted -> ../../run/ozone_lat.formatted
ozone_plev.formatted -> ../../run/ozone_plev.formatted
...
namelist.input - editing required
real.exe -> ../../main/real.exe
wrf.exe -> ../../main/wrf.exe
ndown.exe -> ../../main/ndown.exe
.... (many more)
```



Mesoscale & Microscale Meteorological Laboratory / NCAR 11

Running a Real-data Case

- One must successfully run WPS to prepare data required, and create *met_em.** files for multiple time periods for initial and boundary conditions
- Move or link WPS/metgrid output files to the run directory:

```
cd test/em_real
ln -s ../../../../WPS/met_em.d01.* .
```



Mesoscale & Microscale Meteorological Laboratory / NCAR 12


Running a Real-data Case

- Edit `namelist.input` file for runtime options (*at minimum*, one must edit `&time_control` for start, end and integration times, and `&domains` for grid dimensions)
- Run the real-data initialization program:
`./real.exe` if compiled serially / SMP, or
`mpirun -np N ./real.exe` for a MPI job
 where `N` is the number of processors requested.



Running a Real-data Case

- Successfully running `real.exe` will create model initial and boundary files:



N: the number of time periods processed

`ncdump -v Times wrfbdy_d01`



Running a Real-data Case

- Typing '`ncdump -v Times wrfbdy_d01`' will give you, for a 24 hour period, 6 hourly data interval:
 .. a bunch of prints and at the end:

```
data:
Times =
  "2005-08-28_00:00:00",
  "2005-08-28_06:00:00",
  "2005-08-28_12:00:00",
  "2005-08-28_18:00:00" ;
```

* BC data consists of values at the start of the time interval and rate of change in the time interval.



Running a Real-data Case

- Run the model executable by typing:
`./wrf.exe >& wrf.out &`
 or
`mpirun -np N ./wrf.exe &`
- Successfully running the model will create model history file:
`wrfout_d01_2005-08-28_00:00:00`
Based on start date set in namelist
 and a restart file if `restart_interval` is set to a time within the range of the forecast time:

`wrfirst_d01_2005-08-28_12:00:00`
Exact time at a restart



Running a Real Data Case

wrfout_d01_2005-08-28_00:00:00

Based on start date set in namelist

```
start_year      = 2008, 2008, 2008,
start_month     = 08, 08, 08,
start_day       = 28, 28, 28,
start_hour      = 00, 00, 00,
start_minute    = 00, 00, 00,
start_second    = 00, 00, 00,
end_year        = 2008, 2008, 2008,
end_month       = 08, 08, 08,
end_day         = 29, 29, 29,
end_hour        = 00, 00, 00,
end_minute      = 00, 00, 00,
end_second      = 00, 00, 00,
```



Running an Idealized Case



Running an *Idealized* Case

- An idealized case refers to data in the initial condition file (no need to run WPS)
- If you have compiled an ideal case, you should have:
 - `ideal.exe` – program to create idealized initial condition
 - `wrf.exe` – model executable
- These executables are linked to:
 - `WRF/run`
 - and
 - `WRF/test/em_test-case`

➔ One can go to either directory to run.



Running an *Idealized* Case

Go to the desired *ideal* test case directory: e.g.

```
cd test/em_quarter_ss
```

If there is '`run_me_first.csh`' in the directory, run it first - this links relevant physics data files to the current directory:

```
./run_me_first.csh
```



Running an *Idealized* Case

Then run the ideal initialization program:

```
./ideal.exe
```

The input to this program is typically a sounding file (file named *input_sounding*), or a pre-defined 2D input (e.g. *input_jet* in *em_b_wave* case).

Running *ideal.exe* only creates WRF initial condition file: *wrfinput_d01*



Running an *Idealized* Case

Note that wrfbdy file is not needed for idealized cases.

Instead, the boundary condition options are set in the *namelist.input* file. For example, these are for options in east-west, or x direction:

```
periodic_x      = .true.,  
symmetric_xs    = .false.,  
symmetric_xe    = .false.,  
open_xs         = .false.,  
open_xe         = .false.,
```



Running an *Idealized* Case

- To run the model interactively, type

```
./wrf.exe >& wrf.out &
```

for single processor (serial) or SMP run. Or

```
mpirun -np N ./wrf.exe &
```

for a MPI run (3D cases only)
- Successful running of the model executable will create a model history file called *wrfout_d01_<date>*
e.g. *wrfout_d01_0001-01-01_00:00:00*

Based on start date set in namelist
(dates are important for radiation physics)



Running an *Idealized* Case

wrfout_d01_0001-01-01_00:00:00

Based on start date set in namelist

```
start_year      = 0001, 0001, 0001,  
start_month     = 01, 01, 01,  
start_day       = 01, 01, 01,  
start_hour      = 00, 00, 00,  
start_minute    = 00, 00, 00,  
start_second    = 00, 00, 00,  
end_year        = 0001, 0001, 0001,  
end_month       = 01, 01, 01,  
end_day         = 01, 01, 01,  
end_hour        = 00, 00, 00,  
end_minute      = 120, 120, 120,  
end_second      = 00, 00, 00,
```



Running an *Idealized* Case

- Edit `namelist.input` file to change options.
- For your own case, you may provide a different sounding.
- You may also edit `dyn_em/module_initialize <case>.F` to change other aspects of the initialization (*more on Thur.*)

Note:

- For 2D cases and baroclinic wave case, `ideal.exe` must be run serially
- For all 2D cases, `wrf.exe` must be run serially or with SMP
- For the 1D case, compile and run serially



Basic namelist Options



What is a namelist?

- A Fortran namelist contains a list of *runtime* options for the code to read in during its execution. Use of a namelist allows one to change runtime configuration without the need to recompile the source code.
- Fortran 90 namelist has very specific format, so edit with care:

```
&namelist-record - start  
/  
- end
```
- As a general rule:
 - Multiple columns: domain dependent
 - Single column: value valid for all domains

A namelist file may contain a number of records



namelist record `&time_control`

```
run_days      = 0,  
run_hours     = 24,  
run_minutes   = 0,  
run_seconds   = 0,  
start_year    = 2000, 2000, 2000,  
start_month   = 01, 01, 01,  
start_day     = 24, 24, 24,  
start_hour    = 12, 12, 12,  
start_minute  = 00, 00, 00,  
start_second  = 00, 00, 00,  
end_year      = 2000, 2000, 2000,  
end_month     = 01, 01, 01,  
end_day       = 25, 25, 25,  
end_hour      = 12, 12, 12,  
end_minute    = 00, 00, 00,  
end_second    = 00, 00, 00,  
interval_seconds = 21600,  
history_interval = 180, 60, 60,  
frames_per_outfile = 1000, 1000, 1000,  
restart_interval = 360,  
restart       = .true.,
```

domain 1 option

for nests



Notes on `&time_control`

- `run_*` time variables:
 - Model simulation length: `wrf.exe` and domain 1 only
- `start_*` and `end_*` time variables:
 - Program `real` will use WPS output between these times to produce lateral (and lower) boundary file
 - They can also be used to specify the start and end of simulation times for the coarse grid if `run_*` variables are not set (or set to 0)



Notes on `&time_control`

- `interval_seconds`:
 - Time interval between WPS output times, and lateral BC (and lower BC) update frequency
- `history_interval`:
 - Time interval in minutes when a history output is written (note output is instantaneous)
 - If the `time_step` cannot be evenly divided by `history_interval`, then nearest time step output is used
 - The time stamp in a history file name is the time when the history file is first written, and multiple time periods may be written in one file. e.g. a history file for domain 1 that is first written for 1200 UTC Jan 24 2000 is
`wrfout_d01_2000-01-24_12:00:00`



Notes on `&time_control`

- `frames_per_outfile`:
 - Number of history times written to one file
- `restart_interval`:
 - Time interval in minutes when a restart file is written
 - By default, restart file is not written at hour 0
 - A restart file contains only one time level data, and its valid time is in its file name, e.g. a restart file for domain 1 valid for 0000 UTC Jan 25 2000 is
`wrfrst_d01_2000-01-25_00:00:00`
- `restart`:
 - whether this is a restart run



Notes on `&time_control`

Example 1: all output times are in a single file

```
history_interval = 180, 60, 60,  
frames_per_outfile = 1000, 1000, 1000,  
wrfout_d01_2000-01-24_12:00:00
```

Example 2: each output file only contains a single time

```
history_interval = 180, 60, 60,  
frames_per_outfile = 1, 1, 1,  
wrfout_d01_2000-01-24_12:00:00  
wrfout_d01_2000-01-24_15:00:00  
wrfout_d01_2000-01-24_18:00:00
```



Notes on *restart*

- What is a *restart* run?
 - A restart run is a continuation of a model run
- How to do a *restart* run:
 - In the first run, set *restart_interval* to a value that is within the model integration time
 - A restart file will be created. e.g.
`wrfrst_d01_2000-01-25_00:00:00`
- When doing a restart run:
 - Set *restart* = .true.,
 - Set start time to restart time
 - Set run_* to be the hours remaining in the run



&time_control

```
io_form_history = 2,
io_form_restart = 2,
io_form_input = 2,
io_form_boundary = 2,
```

IO format options:

= 1, binary
 = 2, **netcdf** (most common)
 = 4, PHDF5
 = 5, Grib 1
 = 10, Grib 2
 = 11, pnetCDF

For large files:

io_form_restart = 102 :
 write output in patch
 sizes: fast for large grid
 and useful for restart file



namelist record &domains

```
time_step = 180
time_step_fract_num = 0,
time_step_fract_den = 1,
max_dom = 1,
e_we = 74, 112, 94,
e_sn = 61, 97, 11,
e_vert = 33, 28, 28,
num_metgrid_levels = 32,
num_metgrid_soil_levels = 4
dx = 30000, 10000, 3333,
dy = 30000, 10000, 3333,
eta_levels = 1.0, 0.996, 0.99, 0.98, ... 0.0
p_top_requested = 5000,
```

nest
options



Notes on &domains

- *time_step*, *time_step_fract_num*, *time_step_fract_den*:
 - Time step for model integration in seconds
 - Fractional time step specified in separate integers of numerator and denominator
 - Typically 5 to 6xDX (DX is grid distance in km)
- *e_we*, *e_sn*, *e_vert*:
 - Model grid dimensions (staggered) in X, Y and Z directions, need to match those defined in *geogrid* program
- *num_metgrid_levels*:
 - Number of *metgrid* (input) data levels
- *num_metgrid_soil_levels*:
 - Number of soil data levels in the input data
- ➔ Both can be found by typing `ncdump -h met_em.d01.<date> | more`
- *dx*, *dy*:
 - grid distance: in meters



Notes on &domains

- *p_top_requested*:
 - Pressure value at the model top
 - Constrained by the available data from WPS
 - Default is 5000 Pa (recommended as lowest model top)
- *eta_levels*:
 - Specify your own model levels from 1.0 to 0.0
 - If not specified, program *real* will calculate a set of levels
 - V4 has a new and better way to compute the levels
 - Use a minimum of 33 or more levels with 5000 Pa model top to limit vertical grid distance < 1 km. Use more vertical levels when decreasing horizontal grid sizes.



namelist record &bdy_control

	typical	optional	
spec_bdy_width	= 5,	(10)	
spec_zone	= 1,	(1)	← do not change
relax_zone	= 4,	(9)	
specified	= .true.,		
nested	= .false.,		

May change **relax_zone**
and **spec_bdy_width**
(**spec_zone** + **relax_zone**
= **spec_bdy_width**)

* Wider boundary zone may work
better for coarser driving data



Other namelists

&physics:

- Model physics options

&dynamics:

- Damping, diffusion options
- Advection options
- In 4.0, the hybrid vertical coordinate option is the default.
Turn it off by setting the following for *real* and *wrf*:
hybrid_opt = 0



Where do I start?

- Always start with a *namelist* template provided in a test case directory, whether it is an ideal case, or a real data case.
 - A number of namelist templates are provided in *test/test_<case>/* directories

For example: in *test/em_real/*, there are

namelist.input.4km ~ 4 km grid size
namelist.input.jun01 ~ 10 km grid size
namelist.input.jan00 ~ 30 km grid size



Where do I start?

- For different applications, please refer to p5-38 to 5-40 of the ARW User's Guide:
 - 2 or 4 km microphysics-only runs
 - 20 – 30 km, 2 – 3 day runs
 - Antarctic region
 - Tropical storm forecasting
 - Regional climate
 - Try physics suites (since V3.9)



Where do I start?

- Use document to guide the modification of the namelist values:
 - `run/README.namelist`
 - `test/em_real/examples.namelist`
 - User's Guide, Chapter 5 (online version has the latest)
 - Full list of namelists and their default values can be found in Registry files: [Registry.EM_COMMON](#), `registry.io_boilerplate` (for IO options) and other registry files - look for character string '*namelist*'



To run a job in a different directory..

- Directories `run/` and `test_<case>/` are convenient places to run, but it does not have to be.
- Copy or link the content of these directories to another directory, including **physics data** files, wrf **input** and **boundary** files, wrf **namelist** and **executables**, and you should be able to run a job anywhere on your system.



Check Output



Output After a Model Run

- Standard out/error files:
`wrf.out`, or `rs1.*` files
- Model history file(s):
`wrfout_d01_<date>`
- Model restart file(s), optional
`wrfirst_d01_<date>`



Output from a multi-processor run

The standard out and error will go to the following files for a MPI run:

```
mpirun -np 4 ./wrf.exe ➔
```

<code>rs1.out.0000</code>	<code>rs1.error.0000</code>
<code>rs1.out.0001</code>	<code>rs1.error.0001</code>
<code>rs1.out.0002</code>	<code>rs1.error.0002</code>
<code>rs1.out.0003</code>	<code>rs1.error.0003</code>

There is one pair of files for each processor requested



What to Look for in a standard out File?

Check run log file by typing

```
tail wrf.out, or  
tail rs1.out.0000
```

You should see the following if the job is successfully completed:

```
wrf: SUCCESS COMPLETE WRF
```



How to Check Model History File?

- Use **ncdump**:
`ncdump -v Times wrfout_d01_<date>`
to check output times. Or
`ncdump -v U wrfout_d01_<date>`
to check a particular variable (U)

- Use **ncview** (great tool!)
- Use post-processing tools (see talks later)



What is in a *wrf.out* or *rsl* file?

- Model version, decomposition info:

```
Ntasks in X      2, ntasks in Y      4
WRF V4.0 MODEL
```

- Time taken to compute one model step:

```
Timing for main: time 2000-01-24_20:03:00 on domain 1: 0.89475 elapsed seconds
Timing for main: time 2000-01-24_20:06:00 on domain 1: 0.09011 elapsed seconds
Timing for main: time 2000-01-24_20:09:00 on domain 1: 0.08634 elapsed seconds
Timing for main: time 2000-01-24_20:12:00 on domain 1: 0.09004 elapsed seconds
```

- Time taken to write history and restart file:

```
Timing for Writing wrfout_d01_2000-01-25_00:00:00 for domain 1: 0.07091 elapsed seconds
```

- Any model error prints:

```
5 points exceeded cfl=2 in domain 1 at time 4.200000 MAX AT i,j,k: 123 48 3
cfl,w,d(eta)= 4.165821
```



→ An indication the model has become numerically unstable

Simple Trouble Shooting



Often-seen runtime problems

- module_configure: initial_config: **error reading**

namelist: &dynamics

> Typos or erroneous namelist variables exist in namelist record *&dynamics* in *namelist.input* file

- input_wrf.F: **SIZE MISMATCH:** namelist
ide,jde,num_metgrid_levels= 70 61 27 ; input
data ide,jde,num_metgrid_levels= 74 61 27

> Grid dimensions in error



Often-seen runtime problems

- Segmentation fault** (core dumped)

> Often typing **'unlimit'** or **'ulimit -s unlimited'** or equivalent can help when this happens quickly in a run, and on a small computer

- If you do: `grep cfl rsl.error.*` and see

```
121 points exceeded cfl=2 in domain 1 at time
4.200000 MAX AT i,j,k: 123 48 3 cfl,w,d(eta)=
4.165821
```

> Model becomes unstable due to various reasons. If it happens soon after the start time, check input data, and/or reduce time step.



References

- Information on compiling and running WRF, and a more extensive list of namelist options and their definition / explanations can be found in the [User's Guide, Chapter 5](#)
- Also see nesting talk and demonstration tomorrow.

