



WRF: *More Runtime Options*


Wei Wang
NCAS/NCAR Tutorial, Lincoln UK
October 2019



This material is based upon work supported by the National Center for Atmospheric Research, which is a major facility sponsored by the National Science Foundation under Cooperative Agreement No. 1852977.

More options

- Some useful *runtime* options:
 - Vertical interpolation options (program *real.exe*, [&domains](#))
 - Base state parameters (*real.exe*, [&dynamics](#))
 - Options to use hybrid vertical coordinate (*real.exe*, [&dynamics](#))
 - Defining vertical model levels (*real.exe*, [&domains](#))
 - IO options ([&time_control](#))
 - Physics suites ([&physics](#))
 - Options for long simulations ([&physics](#))
 - Adaptive-time step ([&domains](#))
 - Digital filter ([&dfi_control](#))
 - Global runs ([&dynamics](#))
 - Moving nest ([&domains](#))
 - Tracer ([&dynamics](#)) / trajectory ([&physics](#), [&domains](#))
 - Stochastic parameterization schemes ([&stoch](#))
 - Optional output (various)
 - IO quilting ([&namelist_quilt](#))
- Time series output (surface and profile)




namelist.input

general namelist
records:

`&time_control`
`&domains`
`&physics`
`&dynamics`
`&bdy_control`
`&namelist_quilt`

specialized namelist
records:

`&dfi_control`
`&fdda`
`&stoch`
`&diags`
`&scm`
`&tc`
`&noah_mp`



Look for these in **examples.namelist**



Vertical interpolation options (1)

Program `real` only, &domains:

`interp_type`: in pressure or log pressure

`lagrange_order`: linear or quadratic

`use_surface`: whether to use surface level data



Vertical interpolation options (2)

Program **real** only, &domains:

use_levels_below_ground: whether to use data below the ground


lowest_lev_from_sfc: logical, whether surface data is used to fill the lowest model level values

force_sfc_in_vinterp: number of levels to use surface data, default is 1

extrap_type: how to do extrapolation: 1 - use 2 lowest levels; 2 - constant

t_extrap_type : extrapolation option for temperature: 1 - isothermal; 2 - 6.5 K/km; 3 - adiabatic

Look for these in **examples.namelist**



Base State Parameters

The following could be varied (program *real*, &dynamics):

base_temp



Base state surface temperature

iso_temp

Base state stratosphere temperature (default 200 K)

base_pres_strat



Pressure at which the stratosphere temperature lapse rate changes (since 3.6.1)




Help to improve simulations when model top is higher than 20 km (~ 50 mb)

Hybrid Vertical Coordinate Option

- Decision made when running program `real.exe`, by setting these namelists in `&dynamics`
`hybrid_opt = 2` (0 turns it off)
`eta_c = 0.2` (default)
- New since V3.9
- Default in V4.0





Hybrid Vertical Coordinate Options



Defining Vertical Levels

```
&domains  
auto_levels_opt = 1 or 2  
dzstretch_s = 1.1 ~ 1.3  
dzstretch_z = 1.02 ~ 1.1  
dzbot = 20 ~ 50  
max_dz = < 1000
```




IO Control (1)

History output control in `&time_control`

<code>history_interval:</code>	used often, unit in <u>minutes</u>
<code>history_interval_h:</code>	history output interval in hours
<code>history_interval_s:</code>	history output interval in seconds
<code>history_begin_h:</code>	history output beginning time in hours
<code>history_begin_d:</code>	history output beginning time in days

Look for the list in

`Registry/registry.io_boilerplate`



IO Control (2)

Specify input and output files explicitly in
&time_control

`auxinput1_inname = "/mydata/met_em.d<domain>.<date>"`


: explicitly specify input file (it name and directory)

`history_outname = "/mydata/wrfout_d<domain>_<date>"`

: explicitly specify history output file (its name and directory)

Look for these in

Registry/registry.io_boilerplate



IO Control (3)


Optional history output in `&time_control`

1. Change Registry.EM and **recompile**:

```
state integer rainc ij misc 1 - h03 "RAINCL"
" " "ACCUMULATED TOTAL CUMULUS PRECIPITATION"
state integer rainnc ij misc 1 - h03 "RAINCL"
" " "ACCUMULATED TOTAL GRID SCALE PRECIPITATION"
```

2. Edit namelist.input to output these variables:

```
auxhist3_outname = "rainfall_d<domain>"
auxhist3_interval = 10, 10,
frames_per_auxhist3 = 1000, 1000,
io_form_auxhist3 = 2
```



IO Control (4)

Starting in V3.2, there is an alternative to add/remove output fields at **runtime** (state variables in Registry only)

1. new namelists in `&time_control`:

```
iofields_filename(max_dom) = 'my_output.txt',  
ignore_iofields_warning = .true.
```

2. prepare a text file (`'my_output.txt'`) to select io fields:

```
+:h:3:rainc,rainnc ← syntax in the file
```

3. set other namelists under `&time_control`:

```
auxhist3_outname = "rainfall_d<domain>"  
auxhist3_interval = 10, 10,  
frames_per_auxhist3 = 1000, 1000,  
io_form_auxhist3 = 2
```

See '**Run-Time IO**' section in Chapter 5, User's Guide



Use of physics suite

Since 3.9, physics can be selected as a suite. These represent well-tested physics (&physics).

`physics_suite = 'tropical'`




```
mp_physics = 6, 6,  
cu_physics = 16, 16,  
ra_lw_physics = 4, 4,  
ra_sw_physics = 4, 4,  
bl_pbl_physics = 1, 1,  
sf_sfclay_physics = 91, 91,  
sf_surface_physics = 2, 2,
```

`physics_suite = 'CONUS'`



```
mp_physics = 8, 8,  
cu_physics = 6, 6,  
ra_lw_physics = 4, 4,  
ra_sw_physics = 4, 4,  
bl_pbl_physics = 2, 2,  
sf_sfclay_physics = 2, 2,  
sf_surface_physics = 2, 2,
```

* Note other configuration choices can have an impact on model results



Use of physics suite

To turn an option off for a particular domain:

```
physics_suite = 'tropical'
```




```
cu_physics = -1, 0,
```

To overwrite one or more with other options:

```
physics_suite = 'CONUS'
```



```
cu_physics = 16, 16,  
bl_pbl_physics = 1, 1,  
sf_sfclay_physics = 1, 1,
```



Options for long simulations (1)

Update control for lower boundary fields: allow SST, seaice, monthly vegetation fraction and albedo to be updated regularly during a model run:

sst_update: 0 – no update

1 – update all above fields (in **&physics**)

Set before running **real.exe**, and this will create additional output files: **wrflowinp_d01**, **wrflowinp_d02**, ..

Other namelists required in **&time_control**:

auxinput4_inname = “wrflowinp_d<domain>”

auxinput4_interval = 360, 360,

io_form_auxinput4 = 2 (netCDF)

See ‘**Using sst_update Option**’ in Chapter 5, User’s Guide



Options for long simulations (2) (&physics)

`sst_skin`

diurnal water temp update

`tmn_update`

deep soil temp update, used with `lagday`

`lagday`

averaging time in days

`bucket_mm`



bucket reset value for rainfall
(e.g. `rainc=i_rainc*bucket_mm+rainc`)

`bucket_j`

bucket reset value for radiation fluxes

`spec_exp`


exponential multiplier for boundary zone
ramping (set in *real*, `&bdy_control`). Usually
used with wider boundary zone




Adaptive time steps (1)

- Adaptive-time-step is a way to maximize the model time step while keeping the model numerically stable.
- Good to use for real-time run.
- May not work in combination with other options.


Also see ‘**Using Adaptive Time Stepping**’
section in Chapter 5, UG



Adaptive time steps (2): an example




On average, forecasts finish in 60 min (50-73min) as compared to 79 min standard runtime



Adaptive time steps (3)


Namelist control: **&domains** USE WITH CARE

<code>use_adaptive_time_step</code>	logical switch
<code>step_to_output_time</code>	whether to write at exact history output times
<code>target_cfl</code>	maximum cfl allowed (1.2)
<code>max_step_increase_pct</code>	percentage of time step increase each time; set to 5, 51, 51 (larger value for nest)
<code>starting_time_step</code>	in seconds; e.g. set to $4 \cdot DX$
<code>max_time_step</code>	in seconds; e.g. set to $8 \cdot DX$
<code>min_time_step</code>	in seconds; e.g. set to $4 \cdot DX$



Digital Filter Initialization (DFI) (1)

- DFI is a way to use a low-pass filter to improve model initial conditions
- Useful for short-range model runs (1-6 hours)
- Imbalances in model IC
 - May be introduced by interpolation, different topography, or by objective analysis, and data assimilation
 - May generate spurious gravity waves in the early simulation hours, which could cause erroneous precipitation, numerical instability and degrade subsequent data assimilation




Digital filter initialization (2)

Using DFI

- can construct consistent model fields which do not exist in the initial conditions, e.g. vertical motion, cloud variables
- may reduce the spin-up problem in early simulation hours
- Useful for short-range (1-6 h) forecasts and cycling with data assimilation



DFI is done after program **real**, or data-assimilation step



See ‘**Using Digital Filter Initialization**’, Chap 5, UG.

Digital filter initialization (3)


Use of DFI helps to damp high pressure tendencies in early forecast



Digital filter initialization (4)


DFL:

(Lynch and Huang, 1994)





DDFI:

(Huang and Lynch, 1993)



TDFI:

(Lynch and Huang, 1994)



Digital filter initialization (5)

Namelist control: `&dfi_control`

`dfi_opt`: dfi options: 0: no DFI; 1: DFL; 2: DDFI; 3: TDFI (recommended)

`dfi_nfilter`: filter options 0 - 8, recommended: 7


`dfi_cutoff_seconds` : cutoff period

`dfi_write_filtered_input` : whether to write filtered IC

`dfi_bckstop_*` : stop time for backward integration

`dfi_fwdstop_*` : stop time for forward integration

related namelists: `examples.namelist`



To get pressure tendency data, set `diag_print=1` or `2`

Global application

- Setup in WPS:
`map_proj = 'lat-lon'`
`e_we, e_sn`: `geogrid` will compute dx, dy
See template `'namelist.wps.global'`
- Requires only one-time period data
- In the model stage: (&dynamics)
`fft_filter_lat`: default value is 45 degrees
Caution: some options do not work, or have not been tested with global domain. Start with template `'namelist.input.global'`



See **'Global Run'** section, Chap 5, UG

Automatic moving nest options

Tropical cyclone / typhoon / hurricane applications: (&domains)


vortex_interval: time interval when vortex location is estimated

max_vortex_speed: used to compute the search radius for vortex location

corral_dist: how far the vortex can move near the parent domain boundary (number of grids)

track_level: e.g. 700 or 500 mb

time_to_move: hold nests still until this time




See ‘**Moving Nested Run**’, Chap 5, UG

Tracer option

Add the following in `&dynamics` to activate tracer option (default no. is 8: with array names `tr17_1`, `tr17_2`, ..., `tr17_8`):

```
tracer_opt = 2,
```

One would need some way to initialize the tracer. A simple initialization can be found in program real (`dyn_em/module_initialize_real.F`)



Trajectory option


Add the following in `&physics` to activate trajectory option:

`traj_opt = 1,`

And set the number of trajectories in `&domains`:

`num_traj = 1000,` (default value)

New in V3.9: it can output meteorological variables, as well as chemistry ones, along the trajectories.



Stochastic parameterization schemes

This is a way to stochastically perturb forecasts (**&stoch**)

skebs : = 1, activate the scheme


nens : = N, an integer that controls the random number stream;
a different integer will give a differently perturbed forecast

perturb_bdy : = 1, use SKEB pattern; = 2, use user-provided
pattern (new in 3.5)

sppt : = 1, activate stochastically parameterized pert tendencies

spp : = 1, activate stochastic perturbed parameters in physics

Also see ‘**Option to stochastically perturb forecasts**’
section in Chap 5, UG



Also see <http://www.cgd.ucar.edu/~berner/skebs.html>

Additional Output Option (1)

`prec_acc_dt = 60.:` in `&physics`


Output precipitation in a time interval (e.g. 60 min):

`PREC_ACC_C`, for convective rain

`PREC_ACC_NC`, for explicit rain

`SNOW_ACC_NC`, for explicit snow

(Caution: *May not suitable for use in long runs*)



Additional Output Option (2a)

Since V3.4.1:

`&diags`

`p_lev_diag = 1.`

`num_press_levels = 4,`

`press_levels = 85000,70000,50000,20000`


Output a few met fields on pressure levels :

`U_PL, V_PL, S_PL, T_PL, Q_PL, RH_PL, GHT_PL,`

Output goes to auxiliary stream 23, so need to set

`auxhist23_outname, io_form_auxhist23,`

`auxhist23_interval, frames_per_auxhist23`



Additional Output Option (2b)

Since V3.7.1:

`&diags`

`z_lev_diag = 1.`

`num_z_levels = 4,`

`z_levels = 80,150,300,3000`


Output a few met fields on pressure levels :

`U_ZL, V_ZL, S_ZL, T_ZL, Q_ZL, RH_ZL, GHT_ZL,`

Output goes to auxiliary stream 23, so need to set

`auxhist23_outname, io_form_auxhist23,`

`auxhist23_interval, frames_per_auxhist23`



Additional Output Option (3)

Since V3.9:

`&diags`


`diags_nwp = 1.`

Output a few met fields on model levels :

sealevelp, temperature, geoheight, pressure, umet,
vmc, speed, dir, U10, V10, Q2, T2, RAIN, LIQRAIN,
TPW, RH

Output goes to auxiliary stream 1, so need to set

`auxhist1_outname, io_form_auxhist1,`
`auxhist1_interval, frames_per_auxhist1`



Additional Output Option (4)

`output_diagnostics = 1:` (&time_control)
output max, min, time of max and min, mean value, standard deviation of the mean for 8 surface variables (T2, Q2, TSK, U10, V10, 10 m wind speed, RAINCV, and RAINNCV [time step rain])

```
auxhist3_outname = "wrfxtrm_d<domain>_<date>"  
io_form_auxhist3 = 2  
auxhist3_interval = 1440, 1440,  
frame_per_auxhist3 = 10, 10,
```




Additional Output Option (5)

`nwp_diagnostics = 1: (&time_control)`

Output max 10 m wind speed, max helicity in 2 – 5 km layer, max w in updraft and downdraft below 400 mb, mean w in 2 – 5 km layer, and max column graupel in a time window between history output times.

Data goes to history file.




Additional Output Option (6)

```
do_radar_ref = 1: (&physics)
```

Compute radar reflectivity using parameters used by different microphysics. Works for options mp_physics = 2,4,6,7,8,10,14,16. Option 9, NSSL mp also produce radar reflectivity output.

Data goes to history file.




Additional Output Option (7)

`do_avgflx_em = 1: (&dynamics)`

output history-time-averaged, column-pressure-coupled u, v and w:

`AVGFLX_RUM, AVGFLX_RVM, AVGFLX_RWM`

– useful for driving downstream transport model



Additional Output Option (8)

`afwa*_opt = 1:` (&afwa, with sub-options)

output over 60 diagnostic variables to history file (for example, MSLP, precipitable water, cloud cover, etc.)

See Registry/registry.afwa for full listing.

Data goes to history as well as auxhist2 file.




Additional Output Option (9)

More climate output (from RASM, new in V3.9):

`mean_diag = 1:` (with interval options, &time_control)
`diurnal_diag = 1`

Output time-step and diurnal averaging of a number of surface variables and radiative fluxes at surface and top of atmosphere (e.g. monthly averages)

See run/README.rasm_diag for details, and Registry/registry.rasm_diag for full listing.



Data goes to auxhist5 and auxhist6 files.

IO quilting: &namelist_quilt

I/O quilting control:

nio_tasks_per_group (>0) : allow IO to be done on separate processors. Performance improvement for large domain runs. A value of 2 to 4 works well.

io_groups (>1) : number of I/O streams that the quilting applies.


See ‘**Using IO Quilting**’ section, Chap 5, UG

Other ways to improve IO: 1) p-netCDF; 2) use netCDF4 compression option; 3) use io_form_history=102 to output patches of data



Time Series Output (1)

- It is a special output in text format with file name like
prefix.d<domain>.TS
- It outputs 14 surface variables at every time step:
e.g. 10 m u/v, 2 m T/qv, precipitation, radiation fluxes, surface fluxes
- One file per location (e.g. at weather station), per domain



Time Series Output (2)

- It also outputs profiles of U, V, Th, Qv, PH (levels set by `max_ts_level`, default 15):

prefix.d<domain>.UU

prefix.d<domain>.VV

prefix.d<domain>.TH

prefix.d<domain>.QV

prefix.d<domain>.PH

- One file per location (e.g. at weather station), per domain.




Time Series Output (3)

- Not a namelist option to turn it on
- If output more than 5 locations, use namelist **max_ts_locs** in **&domains**
- Requires a file called '**tslist**' present in working directory (a sample of the file is available in **WRF/run/**)

```
#-----#
# 24 characters for name | pfx |  LAT  |  LON  |
#-----#
Cape Hallett             hallt -72.330  170.250
McMurdo Station          mcm    -77.851  166.713
```


- This file provides a list of locations where you would like to output time series
- More information in **run/README.tslist** and '**Output Time Series**' section, Chapter 5, UG



Time Series Output (4)

Content in hallt.d01.TS:

```
Cape Hallett          1 1 hallt ( 36.710, -79.000) ( 41, 38) (
  36.600, -79.142) 159.6 meters
1      0.050000      1 41 38      275.47397      0.00288
  3.52110      -2.34275 99988.76563      244.81276
0.00000      -29.94841      4.09765      273.90295      278.20197
  0.00000      0.00000      0.00000
1      0.100000      1 41 38      275.56287      0.00282
  3.14414      -2.05875 99956.98438      244.81276
0.00000      -25.64095      4.18446      273.78323      278.18314
  0.00000      0.00000      0.00000
```



Recommended

Start with the **namelist template** in a particular test directory, and the options specified in the file, and make modifications.

Chapter 5 of ARW User's Guide, pages 5-37 – 5-39: examples for various applications; page 34: physics suites.

For special applications in ARW, look for related namelists in the file *examples.namelist* in *test/em_real/* directory.

For more information on global extension, DFI and adaptive time step, read Tech Note, and User's Guide.

