# The WRF Preprocessing System: Description of General Functions

Michael Duda



#### Purpose of this Lecture

In this lecture, our goals are to:

- 1) Understand the purpose of the WPS
- 2) Learn what each component of the WPS does

- The details of *actually running* the WPS are covered in the second WPS lecture
- Advanced usage of the WPS is covered in the third lecture



#### Purpose of the WPS


The purpose of the WPS is to prepare input to WRF for real-data simulations:

- Defines simulation domain and nested domains
- Computes latitude, longitude, map scale factors, Coriolis parameters at every grid point
- Interpolates time-invariant terrestrial data to simulation grids (e.g., terrain height and soil type)
- Interpolates time-varying meteorological fields from another model onto simulation domains




## WRF Modeling System Flowchart

#### WRF Modeling System Flow Chart (for WRFV2)






## WPS Program Flowchart





#### The *geogrid* program



geogrid: think geographical



#### The *geogrid* program

- Define projection, location, and dimensions of simulation domains, including ARW nested domains
- Compute latitude, longitude, map scale factor, and Coriolis parameters at each grid point
- Horizontally interpolate static terrestrial data to each grid point
  - Topography height, land use category, soil type, vegetation fraction, monthly surface albedo, etc.



#### Geogrid: Defining model domains


- First, we choose a map projection to use for the domains
  - The real earth is (roughly) an ellipsoid
  - But WRF computational domains are defined by rectangles in the plane
- NMM uses a rotated lat/lon projection
- ARW can use one of the following projections:
  - Lambert conformal
  - Mercator
  - 3. Polar stereographic




#### Why does ARW support 3 projections?

ARW 2.2.1 requires conformal map projections, and rather than rotate the earth with a single projection, we use different projections for different regions of the globe









#### Geogrid: Defining Model Domains

- Define projection of domains with (at most) the following parameters
  - MAP PROJ: 'lambert', 'mercator', 'polar', or 'rotated II'
- TRUELAT1: First true latitude
   TRUELAT2: Second true latitude (only for Lambert conformal)
   STAND\_LON: The meridian parallel to y-axis

  - All parameters reside in the file *namelist.wps*




\*ARW only

#### Geogrid: Defining Model Domains

- Define the area covered (dimensions and location) by coarse domain using the following:
  - REF\_LAT, REF\_LON: The (lat,lon) of a known location in the domain (by default, the center point of the domain)
  - DX, DY: Grid distance where map factor = 1
  - E\_WE: Number of velocity points in west-east direction for ARW; number of mass points in odd rows for NMM
  - E\_SN: Number of velocity points in south-north direction for ARW; number of rows for NMM




# Geogrid: Defining ARW Domains






#### Geogrid: Defining ARW Domains





# Geogrid: Defining NMM Domains






#### Geogrid: Nesting Basics

- A nested domain is a domain that is wholly contained within its parent domain and that receives information from its parent, and that may also feed information back to its parent
  - A nested domain has exactly one parent
  - A domain may have one or more *children*
- 2-way nests on the same nesting level must not overlap in coverage!




## Geogrid: Nesting Example

Example configuration – 4 domains



Each domain is assigned a domain ID #






#### Geogrid: Defining Nested ARW Domains

- Define the dimensions and location of nested domains using:
  - PARENT\_ID: Which domain is the parent?
  - PARENT\_GRID\_RATIO: What is the ratio between grid spacing in parent to grid spacing in this nest?
  - I\_PARENT\_START: i-coordinate in parent of this nest's lower-left corner
  - J\_PARENT\_START: j-coordinate in parent of this nest's lower-left corner
  - E\_WE: Number of velocity points in west-east direction for ARW
  - E\_SN: Number of velocity points in south-north direction for ARW



## Geogrid: Defining Nested Domains




The grid spacing (dx)
of domain 2 is
determined by grid
spacing of
domain 1 and the
parent\_grid\_ratio

NB: For NMM, the parent\_grid\_ratio is always 3!



## Geogrid: Nesting example






## Geogrid: Interpolating Static Fields

- Given definitions of all computational grids, interpolate terrestrial, time-invariant fields
  - Terrain height
  - Land use categories
  - Soil type (top & bottom layer)
  - Annual mean soil temperature
  - Monthly vegetation fraction
  - Monthly surface albedo



#### Geogrid: Interpolating Static Fields



In general, source data are given on a different projection from the model grid



#### Geogrid: Interpolation Options

- 4-point bilinear
- 16-point overlapping parabolic
- 4-point average (weighted or unweighted)
- 16-point average (weighted or unweighted)
- Grid cell average
- Nearest neighbor
- Breadth-first search



#### Why have so many interpolation options?

- Different interpolators work best for different fields and different relative grid resolutions
  - Some interpolators preserve positive definiteness
  - Some interpolators produce "smoother" fields
  - Some interpolators are best suited for discrete or categorical fields
  - Some are good when going from a fine grid to a coarse grid
- Having a choice of how to interpolate fields is good!
  - We'll see in the third lecture how several different options can be used for different regions of the same field



## Geogrid: Program Flexibility

- The GEOGRID.TBL file determines
  - Which fields will be produced by geogrid
  - What sources of data will be used
  - How the data will be interpolated/smoothed
  - 4. Any derived fields (e.g., dominant cat., df/dx)
- Acceptable defaults exist in GEOGRID.TBL, so user will not generally need to edit the file (but more on this in the third lecture!)



## Geogrid: Program Flexibility

- geogrid is flexible enough to ingest and interpolate new static fields
  - handles either continuous or categorical fields
- New data sets must be written to simple binary format
- User needs to add an entry to the file GEOGRID.TBL



#### Geogrid: Program Output

- The parameters defining each domain, plus interpolated static fields, are written using the WRF I/O API
  - One file per domain for ARW
  - One file per nesting level for NMM
- Filenames: geo em.d0n.nc, or

```
geo_nmm.d01.nc, geo_nmm_nest.l0k.nc
```


(where *n* is the domain ID # and *k* is the nest level)

Example:

```
geo_em.d01.nc geo_nmm.d01.nc geo_em.d02.nc (nest) geo_nmm_nest.l01.nc (nest level) geo_em.d03.nc (nest) geo_nmm_nest.l02.nc (nest level)
```




#### Geogrid: Example Output Fields





#### The *ungrib* program



ungrib: think un+grib



#### The *ungrib* program

- Read GRIB Edition 1 and GRIB Edition 2 files
- Extract meteorological fields
- If necessary, derive required fields from related ones
  - E.g., Compute RH from T, P, and Q
- Write requested fields to an intermediate file format



#### **Ungrib: Vtables**

How does ungrib know which fields to extract?

Using Vtables (think: Variable tables)

- Vtables are files that give the GRIB codes for fields to be extracted from GRIB input files
- One Vtable for each source of data
- Vtables are provided for: NAM 104, NAM 212, GFS, AGRMET, and others



# Ungrib: Example Vtable

GRIB1  Param				UNGRIB   Name	UNGRIB   Units	UNGRIB Description
+ 11   33   34   52   7   11   52   33   34   130   144   144   144   144   144   144   145   85   85   85   87   81   65   223	Type+ 100 100 100 100 105 105 105 105 112 112 112 112 112 112 111	+ 	Level2 +	T   U   V   RH   HGT   T   HGT   T   T   T   T   T   T   T   T   T	K   m s-1   m s-1   %   m s-1   %   m s-1   kg m-3   kg m-3   kg m-3   kg m-3   kg m-3   kg m-1   m   K   K   kg m-2   kg m-2	Temperature  U V Relative Humidity Height Temperature at 2 m Relative Humidity at 2 m U at 10 m V at 10 m Surface Pressure Sea-level Pressure Soil Moist 0-10 cm below grn layer (Up) Soil Moist 10-40 cm below grn layer Soil Moist 40-100 cm below grn layer Soil Moist 100-200 cm below grn layer T 0-10 cm below ground layer (Upper) T 10-40 cm below ground layer (Upper) T 40-100 cm below ground layer (Upper) T 100-200 cm below ground layer (Bottom) Ice flag Land/Sea flag (1=land, 2=sea in GRIB2) Terrain field of source analysis Skin temperature (can use for SST also) Water equivalent snow depth Plant Canopy Surface Water
224   225   +	1 +	0		SOILCAT   VEGCAT	Tab4.213   Tab4.212	

# Ungrib: GRIB2 Vtable Entries

metgrid   Description	•	•	•	GRIB2   Level
Temperature    U			0	100   100   100   100   103   103   103   106
+			· 	·+



#### **Ungrib: Vtables**

What if a data source has no existing Vtable?

#### Create a Vtable

- Get a listing of GRIB codes for fields in the source
  - Check documentation from originating center or use utility such as wgrib, g1print, g2print
- Use existing Vtable as a template
- Check documentation in Chapter 3 of the Users' Guide for more information about Vtables



#### Ungrib: Intermediate File Format

- After extracting fields listed in Vtable, ungrib writes those fields to intermediate format
- For meteorological data sets not in GRIB format, the user may write to intermediate format directly
  - Allows WPS to ingest new data sources; basic programming required of user
  - Simple intermediate file format is easily read/written using routines from WPS (read\_met\_module.F and write\_met\_module.F)



#### **Ungrib: Program Output**

- Output files named FILE: YYYY-MM-DD\_HH
  - YYYY is year of data in the file; MM is month; DD is day; HH is hour
  - All times are UTC
- Example:

FILE:2007-07-24\_00

FILE:2007-07-24\_06

FILE:2007-07-24\_12

ungrib can also write intermediate files in the MM5 or WRF SI format! (To allow for use of GRIB2 data with MM5, for example)




#### **Ungrib: Obtaining GRIB Data**

- Where does one get GRIB data?
  - User's responsibility
  - Some free data are available from NCAR and NCEP. See
  - http://www.mmm.ucar.edu/wrf/users/
    - > under the "Downloads" tab:
      - Some NCEP data in the past year
      - NCEP operational data available daily



## The *metgrid* program



metgrid: think meteorological




#### The *metgrid* program

- Horizontally interpolate meteorological data (extracted by ungrib) to simulation domains (defined by geogrid)
  - Masked interpolation for masked fields
- Rotate winds to WRF grid
  - i.e., rotate so that U-component is parallel to x-axis,
     V-component is parallel to y-axis



# Metgrid: ARW Grid Staggering

- For ARW, wind U-component interpolated to "u" staggering
- Wind V-component interpolated to "v" staggering
- Other meteorological fields interpolated to "θ" staggering by default (can change this!)



A single ARW grid cell, with "u", "v", and "θ" points labeled.



# Metgrid: NMM Grid Staggering

- For NMM, wind U- and V-components interpolated to "V" staggering
- Other meteorological fields interpolated to "H" staggering by default (can change this!)

HVHVHVHVHVHVH

An NMM grid showing "V", and "H" points.



# Metgrid: Interpolation Options\*

- 4-point bilinear
- 16-point overlapping parabolic
- 4-point average (weighted or unweighted)
- 16-point average (weighted or unweighted)
- Grid cell average
- Nearest neighbor
- Breadth-first search




\* These are the same options available for geogrid!

## Metgrid: Masked Interpolation

- Masked fields may only have valid data at a subset of grid points
  - Ex: SST field only valid on water points
- When metgrid interpolates masked fields, it must know which points are invalid (masked)
  - Can use separate mask field (e.g., LANDSEA)
  - Can rely on special values (e.g., 1×10<sup>30</sup>) in field itself to identify masked grid points



## Metgrid: Masked Interpolation



- 🔵 = valid source data
- = masked/invalid data


Suppose we need to interpolate to point X

- Using red points as valid data can give a bad interpolated value!
- Masked interpolation only uses valid blue points to interpolate to X


Not every interpolation option can handle masked points; we'll address this issue in the third lecture



## **Example: Masked Interpolation**



Skin temperature field interpolated from GFS 0.5-deg field with no mask using a sixteen-point interpolator.




Skin temperature field interpolated using masks: GFS water points interpolated to model water points, GFS land points interpolated to model land points.


## Metgrid: Wind Rotation

- Input wind fields (U-component + V-component) are either:
  - Earth-relative: U-component = westerly component; V-component = southerly component
  - Relative to source grid: U-component (V-component) parallel to source model x-axis (y-axis)
- WRF expects wind components to be relative to the simulation grid



## Metgrid: Wind Rotation Example





A wind vector, shown in terms of its U and V components with respect to the source grid.

The same vector, in terms of its U and V components with respect to the WRF simulation grid.

This process may require *two* rotations: one from source grid to earth grid and a second from earth grid to WRF grid



#### Metgrid: Constant Fields

- For short simulations, some fields may be constant
  - E.g., SST or sea-ice fraction
- Use namelist option constants\_name option to specify such fields:
  - CONSTANTS NAME = 'SST FILE:2007-07-24 00'



# Metgrid: Program Flexibility

- metgrid is capable of interpolating both isobaric and native vertical coordinate data sets
- User may specify interpolation methods and related options in the METGRID.TBL file
  - METGRID.TBL file similar in format to the file GEOGRID.TBL



# Metgrid: Program Output


- For coarse domain, one file per time period
  - In ARW, we also get the first time period for all nested grids
- Files contain static fields from geogrid plus interpolated meteorological fields
- Filenames:

```
ARW: met_em.d0n.YYYY-MM-DD_HH:mm:ss.nc (where n is the domain ID #)
```

NMM: met\_nmm.d01.YYYY-MM-DD\_HH:mm:ss.nc




## Metgrid: Example Output






#### **WPS Summary**





#### And finally...

# Vertical interpolation to WRF eta levels is performed in the real program





# Questions?

