

WRF-Var System

WRF Tutorial
January 17, 2008

Syed RH Rizvi
MMM Division, NCAR,
PO Box 3000, Boulder, Colorado,
80307-3000, USA
rizvi@ucar.edu

WRF-Var in the WRF Modeling System

WRF-Var in the WRF Modeling System




WRF-Var

Blue --> Supported by WRF-Var Team

WRF-Var in the WRF Modeling System


1. Prepare BE data (initially use default statistics)



Blue --> Supported by WRF-Var Team


WRF-Var in the WRF Modeling System

2. Prepare background (SI or WPS & real)



WRF-Var in the WRF Modeling System

3. Prepare observations (run 3DVAR_OBSPROC).




Observation Input (y^0)

- Observation input for WRF-Var is processed through observation preprocessor (**3DVAR_OBSPROC**)
- WRF-Var accepts input both in ASCII & BUFR format
- Radar (reflectivity & radial velocity) data input is supplied through a separate file, currently in ASCII format.


WRF-Var in the WRF Modeling System

4. Run WRF-Var.




WRF-Var in the WRF Modeling System

5. Run WRF_BC.




WRF-Var in the WRF Modeling System

6a. Run forecast (cold-start mode).



WRF-Var in the WRF Modeling System

6b. Run forecast (cycling mode).



Background Error (BE) for WRF-Var

- The number 1 question from WRF-Var users is

“What background error are best for my application?”.


Answer:

- Create your own once you have run your system for few weeks.
- Implement, tune, and iterate.

“*gen_be*” utility has been developed at NCAR to calculate BE's.


WRF-Var in the WRF Modeling System

7. WRF-Var/WRF Ultimate Configuration!



WRF-Var Code Overview


WRF-Var



Setup Frame

- **Reads grid dimensions from “namelist.3dvar” file.**
- **Use WRF framework’s distributed memory capability to initialize tile, memory, patch dimensions, etc.**

WRF-Var



Read Namelist

- **Reads WRF-Var data assimilation options from “namelist.3dvar” file.**
- **“namelist.3dvar” file is created automatically at run-time by the DA_Run_WRF_Var.csh script in wrfvar/run.**
- **Performs consistency checks between namelist options.**

namelist.3dvar

```
&record1
MODEL_TYPE = 'WRF',
WRITE_INCREMENTS = .FALSE.,
GLOBAL      = .FALSE.,
PRINT_DETAIL = 0 /

&record2
ANALYSIS_TYPE = '3D-VAR',
ANALYSIS_DATE = '2004-05-01_00:00:00.0000',
ANALYSIS_ACCU = 900 /

&record3
fg_format = 1,
ob_format = 2,
num_fgat_time = 1 /

&record4
PROCESS_OBS = 'YES',
obs_qc_pointer = 0,
Use_SynopObs = .TRUE.,
Use_ShipsObs = .TRUE.,
Use_MetarObs = .TRUE.,
Use_PilotObs = .TRUE.,
Use_SoundObs = .TRUE.,
Use_SattemObs = .TRUE.,
Use_GeoAMVObs = .TRUE.,
Use_PolarAMVObs = .TRUE.,
Use_AirepObs = .TRUE.,
Use_GpspwObs = .TRUE.,
Use_GpsrefObs = .TRUE.,
Use_ProfilerObs = .TRUE.,
Use_BuoyObs = .TRUE.,
Use_SsmiRetrievalObs = .FALSE.,
Use_SsmiTbObs = .FALSE.,
use_ssm1obs = .FALSE.,
use_ssm2obs = .FALSE.,
use_qscatobs = .TRUE.,
use_radarobs = .FALSE.,
Use_Radar_rv = .FALSE.,
Use_Radar_rf = .FALSE.,
check_max_iv = .FALSE.,
use_obs_errfac = .FALSE.,
put_rand_seed = .FALSE.,
omb_set_rand = .FALSE.,
omb_add_noise = .FALSE. /
```

```
&record5
TIME_WINDOW = 3.,
/

&record6
max_ext_its = 1,
EPS         = 1.E-02, 1.E-02, 1.E-02, 1.E-02, 1.E-02, 1.E-02, 1.E-02,,
NTMAX       = 100,
NSAVE       = 4,
WRITE_SWITCH = .FALSE.,
WRITE_INTERVAL = 5 /
```

```
&record7
RF_PASSES = 6,
VAR_SCALING1 = 1.0,
VAR_SCALING2 = 1.0,
VAR_SCALING3 = 1.0,
VAR_SCALING4 = 1.0,
VAR_SCALING5 = 1.0,
LEN_SCALING1 = 1.0,
LEN_SCALING2 = 1.0,
LEN_SCALING3 = 1.0,
LEN_SCALING4 = 1.0,
LEN_SCALING5 = 1.0 /
```

```
&record8
def_sub_domain = .FALSE.,
x_start_sub_domain = 55.0,
y_start_sub_domain = 35.0,
x_end_sub_domain = 80.0,
y_end_sub_domain = 60.0 /
```

```
&record10
Testing_3DVAR = .FALSE.,
Test_Transforms = .FALSE.,
Test_Statistics = .FALSE.,
Interpolate_Stats = .TRUE. /
```


```
&record11
minimisation_option = 2,
write_outer_loop = .FALSE.,
lat_stats_option = .FALSE.,
calculate_cg_cost_function = .FALSE.,
cv_options = 3,
cv_options_hum = 3,
check_rh = 2,
as1 = 0.25, 0.75, 1.5,
as2 = 0.25, 0.75, 1.5,
as3 = 0.25, 0.75, 1.5,
as4 = 0.25, 0.75, 1.5,
as5 = 0.25, 0.75, 1.5,
sfc_assi_options = 1,
set_omb_rand_fac = 1.0,
seed_array1 = 0,
seed_array2 = 0 /
```

```
&record12
balance_type = 1 /
```

```
&record13
vert_corr = 2,
vertical_ip = 0,
vert_evaluate = 1,
max_vert_var1 = 99.0,
max_vert_var2 = 99.0,
max_vert_var3 = 99.0,
max_vert_var4 = 99.0,
max_vert_var5 = 99.0 /
```

```
&pseudo_ob_nl
num_pseudo = 0,
pseudo_x = 165.0,
pseudo_y = 65.0,
pseudo_z = 15.0,
pseudo_val = 1.0,
pseudo_err = 1.0,
pseudo_var = 'u' /
```


WRF-Var



Setup Background (First-Guess)

- **Reads in the first-guess field.**
- **Format depends on namelist option**
- **“fg_format” ; 1= WRF, 2= MM5, 3= global**
- **Extracts necessary fields.**
- **Creates background FORTRAN 90 derived data type**
“xb” e.g. xb % mix, xb % u(:, :, :),


WRF-Var



Setup Background Errors (BE)

- **Reads in background error statistics.**
- **Format depends on namelist option “cv_options”
2=MM5, 3 = GFS-based, 4=Global, 5=WRF regional.**
- **Extracts necessary quantities – eigenvectors, eigenvalues, lengthscales, regression coefficients, etc (see gen_be talk).**
- **Creates background error FORTRAN 90 derived data type “be” e.g. be % v1 % evec(:,:), be % v2 % eval(:), etc,**


WRF-Var



Setup Observations

- **Reads in observations.**
- **Format depends on namelist variable “ob_format”
1 = BUFR, 2 = ASCII “WRF-Var” format.**
- **Creates observation FORTRAN 90 derived data type
“ob” e.g. ob % num_gpspw, ob % metar(:),
ob % sound(:) % u(:), etc,**
- **Identifies Obs outside/inside the domain**


WRF-Var



Calculate Innovation Vector (O-B)

- **Calculates “model equivalent” B of observation O through interpolation and change of variable.**
- **Computes observation minus first guess (O-B) value.**
- **Creates innovation vector FORTRAN 90 derived data type “iv” e.g. iv % metar(:), iv % qscat(:) % u,**
iv % sound(:) % u(:), etc


WRF-Var



Minimize Cost Function

- **(a) Initializes analysis increments to zero.**
- **(b) Computes cost function (if desired).**
- **(c) Computes gradient of cost function.**
- **(d) Uses gradient and sometimes cost function also to calculate new value of analysis control variable (v)**
- **Iterate (b) to (d)**


WRF-Var



Compute Analysis

- **Once WRF-Var has found a converged control variable, convert convert control variable to model space analysis increments**
- **Calculate:**
$$\text{analysis} = \text{first-guess} + \text{analysis increment}$$
- **Performs consistency checks e.g. remove negative humidity etc.**


WRF-Var



Compute Diagnostics

- **Compute O-B, O-A statistics for all observation types and variables.**
- **Compute A-B (analysis increment) statistics for all model variables and levels.**
- **Statistics include minimum, maximum (and their locations), mean and standard deviation.**
- **Compute “specialist diagnostics” for error tuning (fort.45, fort.46, fort.47, fort.50 etc.).**


WRF-Var



Output Analysis

- **Outputs analysis in native model format. Choice is made through namelist option “fg_format”**
 - **1 = WRF, 2 = MM5, etc.**
- **Also output analysis increments (for diagnostic purposes) in native model format. Switch off by setting DA_WRITE_INCREMENTS = .FALSE. in namelist.3dvar.**


WRF-Var




Tidy Up

- **Deallocate dynamically-allocated arrays, structures, etc.**
- **Timing information.**
- **Clean end to WRF-Var.**


Source Code 1: *WRF-Var*




Source Code 2: *wrfvar/da_3dvar*




Source Code 3: *wrfvar/da_3dvar/src*



Source Code 4: *wrfvar/da_3dvar/src/da_qscat*



Source Code 5: *wrfvar/da_3dvar/src/da_qscat/da_qscat.F*



```
module da_qscat

    USE DA_Constants
    USE DA_Define_Structures
    USE DA_Interpolation
    USE DA_Statistics
    USE DA_Tools
    USE PAR_UTIL

    ! The "stats_qscat_type" is ONLY used locally in DA_Qscat:

    TYPE residual_qscat1_type
        REAL :: u ! u-wind.
        REAL :: v ! v-wind.
    END TYPE residual_qscat1_type

    TYPE maxmin_qscat_stats_type
        TYPE (maxmin_type) :: u, v
    END TYPE maxmin_qscat_stats_type

    TYPE stats_qscat_type
        TYPE (maxmin_qscat_stats_type) :: maximum, minimum
        TYPE (residual_qscat1_type) :: average, rms_err
    END TYPE stats_qscat_type

CONTAINS

#include "da_calculate_jo_and_grady_qscat.inc"
#include "da_calculate_residual_qscat.inc"
#include "da_check_max_iv_qscat.inc"
#include "da_get_innov_vector_qscat.inc"
#include "da_oa_stats_qscat.inc"
#include "da_ob_stats_qscat.inc"
#include "da_print_stats_qscat.inc"
#include "da_transform_xtoy_qscat.inc"
#include "da_transform_xtoy_qscat_adj.inc"
#include "DA_Calculate_GradY_Qscat.inc"

end module da_qscat
```

Procedure for adding new Observations

- **Edit DA_Define_Structure.F to add new data type.**
- **Make new observation sub-directory under “src”.**
- **Develop desired programs like getting innovation vector, forward observation operator, tangent linear & its adjoint, gradient & cost function etc. in this new sub-directory.**
- **Input observation (update DA_Obs).**
- **Sometimes it might be needed to add certain grid arrays in Registry.**
- **Link into minimization package (DA_Minimisation)**

DA_Run_WRF-Var.csh (summary)

USER: Define non-default job via environment variables:

e.g.: setenv START_DATE 2004050200 overrides the default.

```
#####  
#USER: DO NOT MAKE CHANGES BELOW (if you do, you're on your own!)  
#####
```

[1.0] Specify default environment variables:

e.g. if (! \$?START_DATE) setenv START_DATE 2004050100 # Analysis date.

[2.0] Perform sanity checks:

e.g. check input observation file exists

[3.0] Prepare for assimilation:

Create WRF-Var V2.1 namelist file (namelist.3dvar).

Create WRF V2.1 namelist file (namelist.input).

#[4.0] Run WRF-Var:

e.g. mpirun -v -np 16 -nolocal -machinefile hosts ./wrfvar.exe >&! /dev/null

Learning To Use WRF-Var

- **Consult WRF-Var documentation at:**

<http://www.mmm.ucar.edu/wrf/WG4>

- **Run through the Online WRF-Var Tutorial available at:**

<http://www.mmm.ucar.edu/wrf/WG4/wrfvar.htm>

- **If still confused, ask questions via:**

wrfhelp@ucar.edu