


The WRF Preprocessing System: Description of General Functions

Michael Duda



Purpose of this Lecture



In this lecture, our goals are to:

- 1) Understand the purpose of the WPS
 - 2) Learn what each component of the WPS does
 - 3) Understand why the components work as they do
-
- The details of *actually running* the WPS are covered in a lecture this afternoon
 - *Advanced features* of the WPS are described on Friday



WRF Modeling System Flowchart


WRF Modeling System Flow Chart





Purpose of the WPS

The purpose of the WPS is to prepare input to WRF for real-data simulations:


1. Defines simulation coarse domain and nested domains
2. Computes latitude, longitude, map scale factors, and Coriolis parameters at every grid point
3. Interpolates time-invariant terrestrial data to simulation grids (e.g., terrain height and soil type)
4. Interpolates time-varying meteorological fields from another model onto simulation domains




WPS Program Flowchart



The *geogrid* program




geogrid: think geographical



The *geogrid* program

- For WRF model domains, geogrid defines:
 - Map projection (all domains must use the same projection)
 - Geographic location of domains
 - Dimensions of domains
- Geogrid provides values for static (time-invariant) fields at each model grid point
 - Compute latitude, longitude, map scale factor, and Coriolis parameters at each grid point
 - Horizontally interpolate static terrestrial data (e.g., topography height, land use category, soil type, vegetation fraction, monthly surface albedo)




Geogrid: Defining model domains


- First, we choose a map projection to use for the domains; why?
 - The real earth is (roughly) an ellipsoid
 - But WRF computational domains are defined by rectangles in the plane
- ARW can use any of the following projections:
 1. Lambert conformal
 2. Mercator
 3. Polar stereographic
 4. Latitude–longitude (for global domain, you *must* choose this projection!)





ARW Projections: Lambert Conformal




Lambert Conformal



- Well-suited for mid-latitudes
- Domain cannot contain either pole
- Domain cannot be periodic in west-east direction
- Either one or two *true latitudes* may be specified
 - If two are given, the order doesn't matter






ARW Projections: Mercator




- Well-suited for low-latitudes
- May be used for “channel” domain (periodic domain in west–east direction)
- A single true latitude is specified
 - Cylinder intersects the earth’s surface at \pm truelat




Mercator




ARW Projections: Polar Stereographic



- Good for high-latitude domains, especially if domain must contain a pole
- A single true latitude is specified






ARW Projections: Cylindrical Equidistant




- Required for global domains
- May be used for regional domains
- Can be used in its normal or rotated aspect

Cylindrical Equidistant





Rotating the Lat-Ion Grid


In certain cases, it may be desirable or necessary to rotate the poles of the projection away from the poles of the earth



unrotated




rotated




Computational grid

- When placing a nest over a region that would otherwise lie within a filtered region
- When using the lat-lon projection for limited area grids

See p. 3-11




Geographic grid





Geogrid: Defining Model Domains

- Define projection of domains using a subset of the following parameters
 - MAP_PROJ: 'lambert', 'mercator', 'polar', or 'lat-lon'
 - TRUELAT1: First true latitude
 - TRUELAT2: Second true latitude (*only for Lambert conformal*)
 - POLE_LAT, POLE_LON: Location of North Pole in WRF computational grid (*only for 'lat-lon'*)
 - STAND_LON: The meridian parallel to *y*-axis
- All parameters reside in the file *namelist.wps*

See p. 3-9 and 3-42



Geogrid: Defining ARW Domains




Geogrid: Defining Model Domains

- Define the area covered (dimensions and location) by coarse domain using the following:
 - **REF_LAT, REF_LON:** The (lat,lon) location of a known location in the domain (*by default, the center point of the domain*)
 - **DX, DY:** Grid distance where map factor = 1
 - For Lambert, Mercator, and polar stereographic: **meters**
 - For (rotated) latitude–longitude: **degrees**
 - **E_WE:** Number of velocity points in west–east direction
 - **E_SN:** Number of velocity points in south–north direction

See p. 3–12 and 3–41




Geogrid: Defining ARW Domains




In ARW, (REF_LAT , REF_LON) can refer to an arbitrary point in the domain by using the variables REF_X and REF_Y

See p. 3-43




Geogrid: Nesting Basics

- A *nested domain* is a domain that is wholly contained within its *parent domain* and that receives information from its parent, and that may also feed information back to its parent
 - A nested domain has exactly one *parent*
 - A domain may have one or more *children*
- 2-way nests on the same *nesting level* must not overlap in coverage!





Geogrid: Nesting Example

Example configuration – 4 domains



Each domain is assigned a *domain ID #*




Geogrid: Defining Nested Domains

- Define the dimensions and location of nested domains using:
 - **PARENT_ID**: Which domain is the parent?
 - **PARENT_GRID_RATIO**: What is the ratio of grid spacing in parent to grid spacing in this nest?
 - **I_PARENT_START**: i -coordinate in parent of this nest's lower-left corner
 - **J_PARENT_START**: j -coordinate in parent of this nest's lower-left corner
 - **E_WE**: Number of velocity points in west-east direction
 - **E_SN**: Number of velocity points in south-north direction


See p. 3-19 and 3-41



Geogrid: Defining Nested Domains




The grid spacing (dx) of domain 2 is determined by grid spacing of domain 1 and the *parent_grid_ratio*



Geogrid: Nesting example


Assuming *parent_grid_ratio* = 3



In ARW, nest dimensions must be $(n * \text{parent_grid_ratio} + 1)$ for some integer n


$$112 = 3 * n + 1 \text{ for } n=37$$

$$97 = 3 * n + 1 \text{ for } n=32$$




Geogrid: Interpolating Static Fields


- Given definitions of all computational grids, geogrid interpolates terrestrial, time-invariant fields
 - Topography height
 - Land use categories
 - Soil type (top layer & bottom layer)
 - Annual mean soil temperature
 - Monthly vegetation fraction
 - Monthly surface albedo



Geogrid: Interpolating Static Fields



In general, source data are given on a different projection from the model grid



Geogrid: Interpolation Options


- 4-point bilinear
- 16-point overlapping parabolic
- 4-point average (simple or weighted)
- 16-point average (simple or weighted)
- Grid cell average
- Nearest neighbor
- Breadth-first search

See p. 3-54



Why have so many interpolation options?

- Different interpolators work best for different fields and different relative grid resolutions
 - Some interpolators preserve positive definiteness
 - Some interpolators produce “smoother” fields
 - Some interpolators are best suited for discrete or categorical fields
 - Some are good when going from a fine grid to a coarse grid
- Having a choice of how to interpolate fields is good!
 - We’ll see in Friday’s WPS lecture how several different options can be used for different regions of the same field




Geogrid: Program Flexibility

- The GEOGRID.TBL file determines
 1. Which fields will be produced by geogrid
 2. What sources of data will be used
 3. How the data will be interpolated/smoothed
 4. Any derived fields (e.g., dominant cat., df/dx)
- Acceptable defaults exist in GEOGRID.TBL, so user will not generally need to edit the file (*but more on this in Friday's WPS lecture!*)




Geogrid: Program Flexibility

- *geogrid* is flexible enough to ingest and interpolate new static fields
 - handles either continuous or categorical fields
- New data sets must be written to simple binary format
- User needs to add an entry to the file
GEOGRID.TBL







Geogrid: Program Output


- The parameters defining each domain, plus interpolated static fields, are written using the WRF I/O API
 - One file per domain for ARW
- Filenames: `geo_em.d0n.nc`
(where *n* is the domain ID #)
- Example:
 - `geo_em.d01.nc`
 - `geo_em.d02.nc` (nest)
 - `geo_em.d03.nc` (nest)



Geogrid: Example Output Fields



The *ungrib* program



ungrib: think un+grib




What is a GRIB file, anyway?

- GRIB is a WMO standard file format for storing regularly-distributed (e.g., gridded) fields
 - “General Regularly-distributed Information in Binary”
- Fields within a GRIB file are compressed with a lossy compression
 - Think of truncating numbers to a fixed number of digits
- A record-based format
- Fields in a file are identified only by code numbers
 - These numbers must be referenced against an external table to determine the corresponding field



The *ungrib* program

- Read GRIB Edition 1 and GRIB Edition 2 files
- Extract meteorological fields
- If necessary, derive required fields from related ones
 - E.g., Compute RH from T, P, and Q
- Write requested fields to an intermediate file format



Ungrib: Vtables

How does ungrib know which fields to extract?

Using Vtables (think: Variable tables)

- Vtables are files that give the GRIB codes for fields to be extracted from GRIB input files
- One Vtable for each source of data
- Vtables are provided for: NAM 104, NAM 212, GFS, AGRMET, and others



Ungrib: Example Vtable

GRIB1 Param	Level Type	From Level1	To Level2	UNGRIB Name	UNGRIB Units	UNGRIB Description
11	100	*		T	K	Temperature
33	100	*		U	m s-1	U
34	100	*		V	m s-1	V
52	100	*		RH	%	Relative Humidity
7	100	*		HGT	m	Height
11	105	2		T	K	Temperature at 2 m
52	105	2		RH	%	Relative Humidity at 2 m
33	105	10		U	m s-1	U at 10 m
34	105	10		V	m s-1	V at 10 m
1	1	0		PSFC	Pa	Surface Pressure
130	102	0		PMSL	Pa	Sea-level Pressure
144	112	0	10	SM000010	kg m-3	Soil Moist 0-10 cm below grn layer (Up)
144	112	10	40	SM010040	kg m-3	Soil Moist 10-40 cm below grn layer
144	112	40	100	SM040100	kg m-3	Soil Moist 40-100 cm below grn layer
144	112	100	200	SM100200	kg m-3	Soil Moist 100-200 cm below gr layer
85	112	0	10	ST000010	K	T 0-10 cm below ground layer (Upper)
85	112	10	40	ST010040	K	T 10-40 cm below ground layer (Upper)
85	112	40	100	ST040100	K	T 40-100 cm below ground layer (Upper)
85	112	100	200	ST100200	K	T 100-200 cm below ground layer (Bottom)
91	1	0		SEAICE	proprtn	Ice flag
81	1	0		LANDSEA	proprtn	Land/Sea flag (1=land,2=sea in GRIB2)
7	1	0		HGT	m	Terrain field of source analysis
11	1	0		SKINTEMP	K	Skin temperature (can use for SST also)
65	1	0		SNOW	kg m-2	Water equivalent snow depth
223	1	0		CANWAT	kg m-2	Plant Canopy Surface Water
224	1	0		SOILCAT	Tab4.213	Dominant soil type category
225	1	0		VEGCAT	Tab4.212	Dominant land use category



Ungrib: GRIB2 Vtable Entries

metgrid	GRIB2	GRIB2	GRIB2	GRIB2
Description	Discp	Catgy	Param	Level
Temperature	0	0	0	100
U	0	2	2	100
V	0	2	3	100
Relative Humidity	0	1	1	100
Height	0	3	5	100
Temperature at 2 m	0	0	0	103
Relative Humidity at 2 m	0	1	1	103
U at 10 m	0	2	2	103
V at 10 m	0	2	3	103
Surface Pressure	0	3	0	1
Sea-level Pressure	0	3	1	101
Soil Moist 0-10 cm below grn layer (Up)	2	0	192	106
Soil Moist 10-40 cm below grn layer	2	0	192	106
Soil Moist 40-100 cm below grn layer	2	0	192	106
Soil Moist 100-200 cm below gr layer	2	0	192	106
Soil Moist 10-200 cm below gr layer	2	0	192	106
T 0-10 cm below ground layer (Upper)	0	0	0	106
T 10-40 cm below ground layer (Upper)	0	0	0	106
T 40-100 cm below ground layer (Upper)	0	0	0	106
T 100-200 cm below ground layer (Bottom)	0	0	0	106
T 10-200 cm below ground layer (Bottom)	0	0	0	106
Ice flag	0	2	0	1
Land/Sea flag (1=land, 0 or 2=sea)	2	0	0	1
Terrain field of source analysis	2	0	7	1
Skin temperature (can use for SST also)	0	0	0	1
Water equivalent snow depth	0	1	13	1
Dominant soil type cat.(not in GFS file)	2	3	0	1
Dominant land use cat. (not in GFS file)	2	0	198	1




Ungrib: Vtables

What if a data source has no existing Vtable?

Create a Vtable

- Get a listing of GRIB codes for fields in the source
 - Check documentation from originating center or use utility such as *wgrib*, *g1print*, *g2print*
- Use existing Vtable as a template
- Check documentation in Chapter 3 of the Users' Guide for more information about Vtables


See p. 3–34



Ungrib: Intermediate File Format

- After extracting fields listed in Vtable, ungrib writes those fields to intermediate format
- For meteorological data sets not in GRIB format, the user may write to intermediate format directly
 - Allows WPS to ingest new data sources; basic programming required of user
 - Simple intermediate file format is easily read/written using routines from WPS ([read_met_module.F](#) and [write_met_module.F](#))

See p. 3-32



Ungrib: Program Output

- Output files named *FILE:YYYY-MM-DD_HH*
 - *YYYY* is year of data in the file; *MM* is month; *DD* is day; *HH* is hour
 - All times are UTC

- Example:

FILE:2007-07-24_00

FILE:2007-07-24_06


FILE:2007-07-24_12

ungrib can also write intermediate files in the MM5 or WRF SI format!
(To allow for use of GRIB2 data with MM5, for example)




Ungrib: Obtaining GRIB Data

- Where does one get GRIB data?
 - User's responsibility
 - Some free data are available from NCAR and NCEP. See
 - <http://www.mmm.ucar.edu/wrf/users/>
 - > under the “Downloads” tab:
 - Some NCEP data in the past year
 - NCEP operational data available daily



The *metgrid* program




metgrid: think meteorological




The *metgrid* program

- Horizontally interpolate meteorological data (*extracted by ungrib*) to simulation domains (*defined by geogrid*)
 - Masked interpolation for masked fields
- Rotate winds to WRF grid
 - i.e., rotate so that U-component is parallel to x -axis, V-component is parallel to y -axis




Metgrid: ARW Grid Staggering

- For ARW, wind U-component interpolated to “u” staggering
- Wind V-component interpolated to “v” staggering
- Other meteorological fields interpolated to “ θ ” staggering by default (*can change this!*)



A single ARW grid cell, with “u”, “v”, and “ θ ” points labeled.



Metgrid: Interpolation Options*


- 4-point bilinear
- 16-point overlapping parabolic
- 4-point average (simple or weighted)
- 16-point average (simple or weighted)
- Grid cell average
- Nearest neighbor
- Breadth-first search

* These are the same options available for geogrid!




Metgrid: Masked Interpolation

- *Masked fields* may only have valid data at a subset of grid points
 - E.g., SST field only valid on water points
- When metgrid interpolates masked fields, it must know which points are invalid (masked)
 - Can use separate mask field (e.g., LANDSEA)
 - Can rely on special values (e.g., 1×10^{30}) in field itself to identify masked grid points



Metgrid: Masked Interpolation




- = valid source data
- = masked/invalid data


Suppose we need to interpolate to point X

- Using **red** points as valid data can give a bad interpolated value!
- Masked interpolation only uses valid **blue** points to interpolate to X


Not every interpolation option can handle masked points; we'll address this issue in the advanced WPS lecture




Example: Masked Interpolation



Skin temperature field interpolated from GFS 0.5-deg field with no mask using a sixteen-point interpolator.



Skin temperature field interpolated using masks: GFS water points interpolated to model water points, GFS land points interpolated to model land points.




Metgrid: Wind Rotation


- Input wind fields (U-component + V-component) are either:
 - **Earth-relative:** U-component = westerly component; V-component = southerly component
 - **Relative to source grid:** U-component (V-component) parallel to source model x-axis (y-axis)
- WRF expects wind components to be relative to the simulation grid



Metgrid: Wind Rotation Example




A wind vector, shown in terms of its U and V components with respect to the source grid.



The same vector, in terms of its U and V components with respect to the WRF simulation grid.

This process may require *two* rotations: one from source grid to earth grid and a second from earth grid to WRF grid




Metgrid: Constant Fields

- For short simulations, some fields may be constant
 - E.g., SST or sea-ice fraction
- Use namelist option `CONSTANTS_NAME` option to specify such fields:
 - `CONSTANTS_NAME = 'SST_FILE:2007-07-24_00'`



Metgrid: Program Flexibility

- *metgrid* is capable of interpolating both isobaric and native vertical coordinate data sets
- User may specify interpolation methods and related options in the METGRID.TBL file
 - METGRID.TBL file similar in format to the file GEOGRID.TBL




Metgrid: Program Output



- For coarse domain, one file per time period
 - In ARW, we also get the first time period for all nested grids
- Files contain static fields from geogrid plus interpolated meteorological fields
- Filenames:

`met_em.d0n.YYYY-MM-DD_HH:mm:ss.nc`



(where n is the domain ID #)



Metgrid: Example Output



WPS Summary



And finally...

Vertical interpolation to WRF eta levels is performed in the *real* program

