


Running the WRF Preprocessing System

Michael Duda



Review

Briefly recall the programs in the WPS





Review

- geogrid (think geographical)
 - Define size/location of model domains and interpolate static terrestrial fields to simulation grids
- ungrib (think <u>un+grib</u>)
 - Extract meteorological fields from GRIB files
- metgrid (think meteorological)
 - Horizontally interpolate meteorological fields (from ungrib) to simulation grids (defined by geogrid)



Overview

- How to run through the WPS for basic cases
 - Basic steps for running the WPS
 - Geogrid
 - Ungrib
 - Metgrid
- WPS utility programs
- Common WPS mistakes



STEP 1: Edit namelist.wps

For geogrid, only the &share and &geogrid namelists need to be edited in namelist.wps

&share

```
wrf_core = 'ARW',
max_dom = 2,
io_form_geogrid = 2,
/
```

&geogrid

```
parent_id
               = 1, 1,
parent_grid_ratio = 1,
i_parent_start = 1, 20,
j_parent_start = 1, 17,
e_{we} = 220, 181,
e_sn
             = 175, 181,
geog_data_res = '5m', '2m',
dx
               = 15000.
dy
               = 15000.
map_proj = 'lambert',
ref_lat = 37.0,
ref_lon = -97.0,
truelat1 = 45.0,
truelat2 = 30.0,
stand_lon = -97.0.
geog_data_path = '/data/static/geog/'
```



STEP 1: Edit namelist.wps



wrf_core = 'ARW', $max_dom = 2$,

 $io_form_geogrid = 2$,

Which WRF core? For ARW, set to 'ARW' For NMM, set to 'NMM'

Total number of model domains, including nests, for ARW.

Format for geogrid output files; 2=netCDF is recommended.

See p. 3-8 and 3-37



STEP 1: Edit namelist.wps

&geogrid

```
parent_id = 1, 1, parent_grid_ratio = 1, 3, i_parent_start = 1, 20, j_parent_start = 1, 17,
```

Nesting: Who is the parent?
What is the grid ratio for each nest? Where is it located in its parent?

Domain sizes: How many grid points does the domain have? What is the grid spacing?

e_we = 220, 181, e_sn = 175, 181, dx = 15000, dy = 15000,

 $geog_data_res = '5m', '2m',$

. . .

See p. 3-9, 3-19, and 3-38

Static data: What resolution of source data to interpolate from for each domain? '30s', '2m', '5m', or '10m'?



STEP 1: Edit namelist.wps

&geogrid

. . .

```
map_proj = 'lambert',

ref_lat = 37.0,

ref_lon = -97.0,

truelat1 = 45.0,


truelat2 = 30.0,

stand_lon = -97.0,
```

Map projection: What projection to use? What are the parameters of the projection?

See p. 3-9 and 3-40

geog_data_path = '/data/static/geog/'



Static data: Where are the data directories (e.g., topo_30s) located?

See p. 3-41



STEP 2: Make sure GEOGRID.TBL is linked to the correct version of GEOGRID.TBL

- There are multiple GEOGRID.TBL files to support multiple dynamical cores in WRF
- GEOGRID.TBL.ARW must be used for ARW
- GEOGRID.TBL.NMM must be used for NMM

> ls geogrid/GEOGRID.TBL

GEOGRID.TBL -> GEOGRID.TBL.ARW



STEP 3: Run geogrid.exe

Parsed 11 entries in GEOGRID.TBL

Processing domain 1 of 2

Processing XLAT and XLONG

Processing MAPFAC

Processing F and E

Processing ROTANG

Processing LANDUSEF

Calculating landmask from LANDUSEF

Processing HGT_M

Successful completion of geogrid.

Geogrid processes each domain individually. There will be one section of messages for each domain.

Calculating landmask from LANDUSEF
Processing HGT_M

will be written to the screen and to the screen and to the screen land to the geogrid.log file.




STEP 4: Check that geogrid ran successfully

If geogrid ran sucessfully, this message should be printed:

If there was an error, check for an ERROR or WARNING message in the geogrid.log file, or for a system error, like "Segmentation fault".







STEP 1: Edit namelist.wps

For ungrib, only the &share and &ungrib namelists need to be edited

```
&share
  wrf_core = 'ARW',
  max_dom = 2,
  start_date = '2006-04-01_00:00:00',
  end_date = '2006-04-01_12:00:00',
  interval_seconds = 21600
  io_form_geogrid = 2,
/
```



STEP 1: Edit namelist.wps


&share

```
wrf_core = 'ARW',
max_dom = 2,
```

```
start_date = '2006-04-01\_00:00:00', end_date = '2006-04-01\_12:00:00',
```

 $interval_seconds = 21600$

io_form_geogrid = 2,



Data frequency: How many seconds between output files for ungrib? E.g., 10800 s = 3 hrs

See p. 3-14, and 3-38



STEP 1: Edit namelist.wps

&ungrib
out_format = 'WPS',
prefix = 'GFS',

Intermediate file format: Which format to use for intermediate files? 'WPS', 'SI', or 'MM5' are possible; 'WPS' is recommended.

Intermediate file names: Gives prefix for intermediate files.

Prefix can include a path.

E.g., 'XZY' would give intermediate files named XYZ: yyyy-mm-dd_hh.



See p. 3-14, 3-23, and 3-41

STEP 2: Link the correct Vtable to the file name "Vtable" in the run directory

- Some Vtables are provided with WPS in the wps/ ungrib/Variable_Tables directory
 - E.g., Vtable.GFS, Vtable.SST, Vtable.ECMWF

See p. 3-15

- Ungrib always expects to find a file named
 Vtable in the run directory
 - > In -s ungrib/Variable_Tables/Vtable.GFS Vtable
 - > Is Vtable

Vtable -> ungrib/Variable_Tables/Vtable.GFS



STEP 3: Link GRIB files to the correct file names in the run directory

- Ungrib always expects GRIB files to be named GRIBFILE.AAA, GRIBFILE.AAB, GRIBFILE.AAC, etc., in the run directory
- The link_grib.csh script can be used to link GRIB files to these file names:
 - > link_grib.csh /data/GRIB/GFS/gfs*

See p. 3-15

> Is GRIBFILE.*

GRIBFILE.AAA -> /data/GRIB/GFS/gfs_060401_00_00



STEP 4: Run ungrib.exe

Inventory for date = 2006-08-16 12:00:00

PRES	TT	UU	VV	RH	HGT		
2013.0	0	0	0	0	0	0	
2001.0	X	X	X	X	0	X	
1000.0	X	X	X	X	X		
975.0	X	X	X	X	X		
950.0	X	X	X	X	X		
925.0	X	X	X	X	X		
900.0	X	X	X	X	X		




STEP 5: Check that ungrib ran successfully

If ungrib ran successfully, this message should be printed:

If there was an error, check for error message in ungrib's printout or in the ungrid.log file.

Common errors are related to incorrect date specifications in the &share namelist, or because GRIB2 data was used with a version of WPS compiled without GRIB2 libraries.





STEP 1: Edit namelist.wps

For metgrid, only the &share and &metgrid namelists need to be edited

```
&share wrf_c
```



STEP 1: Edit namelist.wps

&share

```
wrf_core = 'ARW',
max_dom = 2,
```

```
start_date = '2006-04-01\_00:00:00', '2006-04-01\_00:00:00', end_date = '2006-04-01\_12:00:00', '2006-04-01\_00:00:00',
```

```
interval_seconds = 21600
io_form_geogrid = 2,
```

Data time range: Time range to process for each domain. Usually, only the initial time is needed for ARW nested domains.

See p. 3-17 and 3-37



STEP 1: Edit namelist.wps

Intermediate file prefixes: Prefix (or prefixes) of intermediate files to interpolate to model domain. Should match prefix given to ungrib.

&metgrid

fg_name = 'GFS',

constants_name = 'SST:2006-04-01_00',

io_form_metgrid = 2,

See p. 3-17 and 3-24

Constant fields: Optional name of an intermediate file with fields to be used for every time period.

Metgrid I/O format: Which I/O format to use for metgrid output? 2=netCDF is recommended.

See p. 3-17, and 3-41



STEP 2: Make sure METGRID.TBL is linked to the correct version of METGRID.TBL

- There are multiple METGRID.TBL files to support multiple dynamical cores in WRF
- METGRID.TBL.ARW should be used for ARW
- METGRID.TBL.NMM should be used for NMM

> ls metgrid/METGRID.TBL

METGRID.TBL -> METGRID.TBL.ARW



STEP 3: Run metgrid.exe

```
Processing domain 1 of 2
    SST:2006-04-01 00
```

```
Processing 2006-04-01 00
   GFS
```

Processing 2006-04-01 06 **GFS**

Processing 2006-04-01 12 **GFS**

Processing domain 2 of 2 SST:2006-04-01 00 Processing 2006-04-01 00 **GFS**

Successful completion of metgrid.

Fields from constant files (given using constants name) are processed before any time varying fields.

Metgrid processes all time period for one domain before processing for the next domain




STEP 4: Check that metgrid ran successfully

If metgrid ran successfully, this message should be printed:

If there was an error, check for an ERROR or WARNING message in the metgrid.log file, or for a system error, like "Segmentation fault".



After running metgrid, we should have files similar to these





Overview

- How to run through the WPS for basic cases
 - Basic steps for running WPS
 - Geogrid
 - Ungrib
 - Metgrid
- WPS utility programs
- Common WPS mistakes



WPS Utility Programs

- Besides geogrid, ungrib, and metgrid, some simple utility programs are distributed with WPS:
 - For checking contents of intermediate format files
 - For listing contents of GRIB1 & GRIB2 files
 - To assist in locating domains
 - For computing 3d pressure field for ECMWF data
- Some programs use NCAR Graphics libraries for plotting
 - For these utilities, NCAR Graphics must be installed



See p. 3-27

WPS Utility Programs

The utility programs that come with WPS can be helpful when diagnosing problems with WPS output


- All utilities are found in the **WPS/util** directory
- Users are encouraged to make use of these utilities to examine WPS input and output files



Utility: plotgrids.ncl

The *plotgrids.ncl* script plots the locations of grids defined in *namelist.wps*

- plotgrids can be used to iteratively refine the locations of grids.
- plotgrids.ncl uses the namelist.wps file only, so there is no need to run geogrid first!





Utility: rd_intermediate


The rd_intermediate lists information about the fields found in an intermediate-format file

```
TT = GIJIT
UNITS = K DESCRIPTION = Temperature
DATE = 2000-01-24 12:00:00 FCST = 0.000000
SOURCE = unknown model from NCEP GRID 212
LEVEL = 200100.000000
I,J DIMS = 185, 129
IPROJ = 1
  REF X, REF Y = 1.000000, 1.000000
  REF LAT, REF LON = 12.190000, -133.459000
  DX, DY = 40.635250, 40.635250
  TRUELAT1 = 25.000002
DATA(1,1)=295.910950
```



Utility: plotfmt

The plotfmt program plots the fields in the ungrib intermediate-formatted files






Utility: int2nc + plotfmt_nc.ncl


The int2nc program converts an ungrib intermediate file to a standard NetCDF file

Users may then visualize fields with ncview, NCL, or other graphical


packages:



Visualize NetCDF intermediate fields using plotfmt_nc.ncl script



Visualize NetCDF intermediate fields using neview



Utility: g1print and g2print

The *g1print* and *g2print* programs list the contents of a GRIB1 or GRIB2 file:

	Prod Disc	Cat	Param num	Lvl code	Lvl one	Lvl two	Name	Time	Fcst hour
1	0	3	5	100	100000	0	HGT	2006-08-16 12:00:00	00
2	0	3	5	100	97500	0	HGT	2006-08-16_12:00:00	00
3	0	3	5	100	95000	0	HGT	2006-08-16_12:00:00	00
4	0	3	5	100	92500	0	HGT	2006-08-16_12:00:00	00
5	0	3	5	100	90000	0	HGT	2006-08-16_12:00:00	00
6	0	3	5	100	85000	0	HGT	2006-08-16_12:00:00	00
7	0	3	5	100	80000	0	HGT	2006-08-16_12:00:00	00
8	0	3	5	100	75000	0	HGT	2006-08-16_12:00:00	00
9	0	3	5	100	70000	0	HGT	2006-08-16_12:00:00	00
10	0	3	5	100	65000	0	HGT	2006-08-16_12:00:00	00



Utility: calc_ecmwf_p

The calc_ecmwf_p utility creates intermediate files with a pressure (and possibly GHT and RH) field

FILE:2009-08-27_00

PSFC / LOGSFP SOILHGT / SOILGEO TT SPECHUMD

emcwf_coeffs

0	0.000000	0.000000	0.0000	
1	2.000040	0.000000	0.0200	0.0100
2	3.980832	0.000000	0.0398	0.0299
3	7.387186	0.000000	0.0739	0.0568
4	12.908319	0.000000	0.1291	0.1015
5	21.413612	0.000000	0.2141	0.1716
6	33.952858	0.000000	0.3395	0.2768
7	51.746601	0.000000	0.5175	0.4285
8	76.167656	0.000000	0.7617	0.6396
9	108.715561	0.000000	1.0872	0.9244

calc_ecmwf_p.exe

PRES:2009-08-27_00

PRESSURE RH GHT

See p. 3-28



Overview

- How to run through the WPS for basic cases
 - Basic steps for running WPS
 - Geogrid
 - Ungrib
 - Metgrid
- WPS utility programs
- Common WPS mistakes



Common WPS Mistakes

1) All 3-d fields must have same number of levels in metgrid

```
WRF_DEBUG: Warning DIM 4 , NAME

num_metgrid_levels REDIFINED by var GHT 27

26 in wrf_io.F90 line 2347

ERROR: Error in ext pkg write field
```

- This is usually corrected by ensuring that all 3-d meteorological fields have surface level data
- Try setting debug_level=1000 in &share namelist, and checking metgrid.log for a table showing which fields are available at each level



Common WPS Mistakes

- 2) When using a regional data set (e.g., NAM), ensure that model domain is completely covered by the data
 - The metgrid program will stop if the model domain has grid points that are not covered by data
- 3) For native vertical coordinate data sets (e.g., RUCb, ECMWF), ensure that both pressure and geopotential height fields are available



Questions?

