


# The Advanced Research WRF (ARW) Dynamics Solver

1. Terrain, vertical coordinate
2. Equations and variables
3. Time integration scheme
4. Grid staggering
5. Advection (transport) and conservation
6. Time step parameters
7. Filters
8. Map projections and global configuration




## Dynamics: 1. Terrain, vertical coordinate

Hydrostatic pressure  $\pi$

Column mass  $\mu = \pi_s - \pi_t$   
(per unit area)

Vertical coordinate  $\eta = \frac{(\pi - \pi_t)}{\mu}$

Layer mass  $\mu \Delta \eta = \Delta \pi = g \rho \Delta z$   
(per unit area)



Conserved state (prognostic) variables:

$$\mu, U = \mu u, V = \mu v, W = \mu w, \Theta = \mu \theta$$

Non-conserved state variable:  $\phi = gz$

## Dynamics: 2. Equations and variables – moist equations

Moist Equations:

$$\frac{\partial U}{\partial t} + \alpha \mu_d \frac{\partial p}{\partial x} + \frac{\alpha}{\alpha_d} \frac{\partial p}{\partial \eta} \frac{\partial \phi}{\partial x} = - \frac{\partial U u}{\partial x} - \frac{\partial \Omega u}{\partial \eta}$$

$$\frac{\partial W}{\partial t} + g \left( \mu_d - \frac{\alpha}{\alpha_d} \frac{\partial p}{\partial \eta} \right) = - \frac{\partial U w}{\partial x} - \frac{\partial \Omega w}{\partial \eta}$$

$$\frac{\partial \mu_d}{\partial t} + \frac{\partial U}{\partial x} + \frac{\partial \Omega}{\partial \eta} = 0$$

$$\frac{\partial \Theta}{\partial t} + \frac{\partial U \theta}{\partial x} + \frac{\partial \Omega \theta}{\partial \eta} = \mu Q$$

$$\frac{d\phi}{dt} = gw$$

$$\frac{\partial (\mu_d q_{v,l})}{\partial t} + \frac{\partial (U q_{v,l})}{\partial x} + \frac{\partial (\Omega q_{v,l})}{\partial \eta} = \mu Q_{v,l}$$

Diagnostic relations:  $\frac{\partial \phi}{\partial \eta} = -\alpha_d \mu_d p = \left( \frac{R_d \Theta_m}{p_o \mu_d \alpha_d} \right)^\gamma, \Theta_m = \Theta \left( 1 + \frac{R_v}{R_d} q_v \right)$

## Dynamics: 2. Equations and variables – velocities

Vertical momentum eqn. 
$$\frac{\partial W}{\partial t} + g \left( \mu_d - \frac{\alpha}{\alpha_d} \frac{\partial p}{\partial \eta} \right) = - \frac{\partial U w}{\partial x} - \frac{\partial \Omega w}{\partial \eta}$$

Subscript  $d$  denotes dry, and


$$\alpha_d = \frac{1}{\rho_d} \quad \alpha = \alpha_d (1 + q_v + q_c + q_r \dots)^{-1}$$

$$\rho = \rho_d (1 + q_v + q_c + q_r \dots)$$

covariant ( $u, \omega$ ) and  
contravariant  $w$  velocities

$$u = \frac{dx}{dt}, \quad w = \frac{dz}{dt}, \quad \omega = \frac{d\eta}{dt}$$

$$U = \mu u, \quad W = \mu w, \quad \Omega = \mu \omega$$



## Dynamics: 3. Time integration scheme

### 3<sup>rd</sup> Order Runge-Kutta time integration

$$\text{advance } \phi^t \rightarrow \phi^{t+\Delta t}$$

$$\phi^* = \phi^t + \frac{\Delta t}{3} R(\phi^t)$$

$$\phi^{**} = \phi^t + \frac{\Delta t}{2} R(\phi^*)$$

$$\phi^{t+\Delta t} = \phi^t + \Delta t R(\phi^{**})$$


$$\text{Amplification factor } \phi_t = i k \phi; \quad \phi^{n+1} = A \phi^n; \quad |A| = 1 - \frac{(k \Delta t)^4}{24}$$

## Dynamics: 3. Time integration scheme

### Phase and amplitude errors for LF, RK3

Oscillation  
equation  
analysis


$$\psi_t = i k \psi$$



## Dynamics: 3. Time integration scheme – time splitting

$$U_t = L_{\text{fast}}(U) + L_{\text{slow}}(U)$$


### 3<sup>rd</sup> order Runge-Kutta, 3 steps



- RK3 is 3<sup>rd</sup> order accurate for linear eqns, 2<sup>nd</sup> order accurate for nonlinear eqns.
- Stable for centered and upwind advection schemes.
- Stable for Courant number  $U \Delta t / \Delta x < 1.73$
- Three  $L_{\text{slow}}(U)$  evaluations per timestep.

### Dynamics: 3. Time integration scheme - implementation

Begin time step



End time step

### Dynamics: 3. Time integration scheme – perturbation variables

Introduce the perturbation variables:

$$\phi = \bar{\phi}(\bar{z}) + \phi', \mu = \bar{\mu}(\bar{z}) + \mu';$$

$$p = \bar{p}(\bar{z}) + p', \alpha = \bar{\alpha}(\bar{z}) + \alpha'$$

Note –  $\phi = \bar{\phi}(\bar{z}) = \bar{\phi}(x, y, \eta)$ ,  
likewise  $\bar{p}(x, y, \eta), \bar{\alpha}(x, y, \eta)$

Reduces horizontal pressure-gradient errors.

For small time steps, recast variables as perturbations from time  $t$

$$U' = U'^t + U'', V' = V'^t + V'', W' = W'^t + W'',$$

$$\Theta' = \Theta'^t + \Theta'', \mu' = \mu'^t + \mu'', \phi' = \phi'^t + \phi'';$$

$$p' = p'^t + p'', \alpha' = \alpha'^t + \alpha''$$

Allows vertical pressure gradient to be expressed in terms of  $\phi''$ .

### Dynamics: 3. Time integration scheme – acoustic step

(Without expanding variables into perturbation form)

$$U^{\tau+\Delta\tau} \quad \frac{\partial U}{\partial t} + \left( \mu_d \alpha \frac{\partial p}{\partial x} + \frac{\alpha}{\alpha_d} \frac{\partial p}{\partial \eta} \frac{\partial \phi}{\partial x} \right)^\tau = R_U^t$$

$$\mu_d^{\tau+\Delta\tau} \quad \Omega^{\tau+\Delta\tau} \quad \frac{\partial \mu_d}{\partial t} + \frac{\partial U^{\tau+\Delta\tau}}{\partial x} + \frac{\partial \Omega^{\tau+\Delta\tau}}{\partial \eta} = 0$$

$$\Theta^{\tau+\Delta\tau} \quad \frac{\partial \Theta}{\partial t} + \left( \frac{\partial U \Theta^t}{\partial x} + \frac{\partial \Omega \Theta^t}{\partial \eta} \right)^{\tau+\Delta\tau} = R_\Theta^t$$

$$W^{\tau+\Delta\tau} \quad \left\{ \begin{array}{l} \frac{\partial W}{\partial t} + g \left( \mu_d - \frac{\alpha}{\alpha_d} \frac{\partial p}{\partial \eta} \right)^\tau = R_W^t \\ \mu_d^t \frac{\partial \phi}{\partial t} + U^{\tau+\Delta\tau} \frac{\partial \phi^t}{\partial x} + \Omega^{\tau+\Delta\tau} \frac{\partial \phi^t}{\partial \eta} - g \bar{W}^\tau = R_\phi^t \end{array} \right.$$

- Forward-backward differencing on  $U, \Theta$ , and  $\mu$  equations
- Vertically implicit differencing on  $W$  and  $\phi$  equations

### Dynamics: 3. Time integration scheme – hydrostatic option

Instead of solving vertically implicit equations for  $W$  and  $\phi$

Integrate the hydrostatic equation to obtain  $p(\pi)$ :


$$\frac{\partial p}{\partial \eta} = \left( \frac{\alpha_d}{\alpha} \right)^t \mu_d$$

Recover  $\alpha$  and  $\phi$  from:  $p = \left( \frac{R_d \Theta_m}{p_0 \mu_d \alpha_d} \right)^\gamma, \Theta_m = \Theta \left( 1 + \frac{R_v}{R_d} q_v \right),$

and  $\frac{\partial \phi}{\partial \eta} = -\mu_d \alpha_d$

$W$  is no longer required during the integration.

#### Dynamics: 4. Grid staggering – horizontal and vertical



WRF Tutorial July 2016

Bill Skamarock (skamaroc@ucar.edu)

#### Dynamics: 5. Advection (transport) and conservation

2<sup>nd</sup>, 3<sup>rd</sup>, 4<sup>th</sup>, 5<sup>th</sup> and 6<sup>th</sup> order centered and upwind-biased schemes are available in the ARW model.

Example: 5<sup>th</sup> order scheme

$$\frac{\partial(U\psi)}{\partial x} = \frac{1}{\Delta x} \left( F_{i+\frac{1}{2}}(U\psi) - F_{i-\frac{1}{2}}(U\psi) \right)$$

where

$$F_{i-\frac{1}{2}}(U\psi) = U_{i-\frac{1}{2}} \left\{ \frac{37}{60}(\psi_i + \psi_{i-1}) - \frac{2}{15}(\psi_{i+1} + \psi_{i-2}) + \frac{1}{60}(\psi_{i+2} + \psi_{i-3}) \right\} \\ - \text{sign}(1, U) \frac{1}{60} \left\{ (\psi_{i+2} - \psi_{i-3}) - 5(\psi_{i+1} - \psi_{i-2}) + 10(\psi_i - \psi_{i-1}) \right\}$$

WRF Tutorial July 2016

Bill Skamarock (skamaroc@ucar.edu)

#### Dynamics: 5. Advection (transport) and conservation

For constant U, the 5<sup>th</sup> order flux divergence tendency becomes

$$\Delta t \frac{\delta(U\psi)}{\Delta x} \Big|_{5th} = \Delta t \frac{\delta(U\psi)}{\Delta x} \Big|_{6th} \\ - \underbrace{\left[ \frac{U\Delta t}{\Delta x} \frac{1}{60} (-\psi_{i-3} + 6\psi_{i-2} - 15\psi_{i-1} + 20\psi_i - 15\psi_{i+1} + 6\psi_{i+2} - \psi_{i+3}) \right]}_{\frac{Cr}{60} \frac{\partial^6 \psi}{\partial x^6} + H.O.T.}$$

The odd-ordered flux divergence schemes are equivalent to the next higher ordered (even) flux-divergence scheme plus a dissipation term of the higher even order with a coefficient proportional to the Courant number.

WRF Tutorial July 2016

Bill Skamarock (skamaroc@ucar.edu)

#### Dynamics: 5. Advection (transport) and conservation

##### Maximum Courant Number for Advection

$$C_a = U\Delta t / \Delta x$$

Time Integration Scheme	Advection Scheme				
	2 <sup>nd</sup>	3 <sup>rd</sup>	4 <sup>th</sup>	5 <sup>th</sup>	6 <sup>th</sup>
Leapfrog (g=0.1)	0.91	U	0.66	U	0.57
RK2	U	0.90	U	0.39	U
RK3	1.73	1.63	1.26	1.43	1.09


U = unstable

(Wicker & Skamarock, 2002)

WRF Tutorial July 2016

Bill Skamarock (skamaroc@ucar.edu)

## Dynamics: 5. Advection (transport) and conservation – dry-air mass



Mass in a control volume is proportional to

$$(\Delta x \Delta \eta)(\mu)^t$$

since  $\mu(x)\Delta\eta = \Delta\pi = -g\rho\Delta z$

## Dynamics: 5. Advection (transport) and conservation – dry-air mass

Mass in a control volume  $(\Delta x \Delta \eta)(\mu)^t$   
2D example

Mass conservation equation

$$\Delta t^{-1}(\Delta x \Delta \eta) \cdot [(\mu)^{t+\Delta t} - (\mu)^t] = [(\mu u \Delta \eta)_{x-\Delta x/2, \eta} - (\mu u \Delta \eta)_{x+\Delta x/2, \eta}] + [(\mu \omega \Delta x)_{x, \eta-\Delta \eta/2} - (\mu \omega \Delta x)_{x, \eta+\Delta \eta/2}]$$

Change in mass over a time step


mass fluxes through control volume faces

## Dynamics: 5. Advection (transport) and conservation – dry-air mass

Mass in a control volume  $(\Delta x \Delta \eta)(\mu)^t$

Mass conservation equation

$$\Delta t^{-1}(\Delta x \Delta \eta) \cdot [(\mu)^{t+\Delta t} - (\mu)^t] = [(\mu u \Delta \eta)_{x-\Delta x/2, \eta} - (\mu u \Delta \eta)_{x+\Delta x/2, \eta}] + [(\mu \omega \Delta x)_{x, \eta-\Delta \eta/2} - (\mu \omega \Delta x)_{x, \eta+\Delta \eta/2}]$$




## Dynamics: 5. Advection (transport) and conservation – dry-air mass

Mass in a control volume  $(\Delta x \Delta \eta)(\mu)^t$

Mass conservation equation


$$\Delta t^{-1}(\Delta x \Delta \eta) \cdot [(\mu)^{t+\Delta t} - (\mu)^t] = [(\mu u \Delta \eta)_{x-\Delta x/2, \eta} - (\mu u \Delta \eta)_{x+\Delta x/2, \eta}] + [(\mu \omega \Delta x)_{x, \eta-\Delta \eta/2} - (\mu \omega \Delta x)_{x, \eta+\Delta \eta/2}]$$

Vertical fluxes through the horizontal control-volume faces



## Dynamics: 5. Advection (transport) and conservation – dry-air mass

The same mass fluxes are used for neighboring grid cells - hence mass is conserved locally and globally.



## Dynamics: 5. Advection (transport) and conservation – scalars

Mass in a control volume  $(\Delta x \Delta \eta)(\mu)^t$

Scalar mass  $(\Delta x \Delta \eta)(\mu \phi)^t$

Mass conservation equation:

$$\Delta t^{-1}(\Delta x \Delta \eta) \cdot [(\mu)^{t+\Delta t} - (\mu)^t] = [(\mu u \Delta \eta)_{x-\Delta x/2, \eta} - (\mu u \Delta \eta)_{x+\Delta x/2, \eta}] + [(\mu \omega \Delta x)_{x, \eta-\Delta \eta/2} - (\mu \omega \Delta x)_{x, \eta+\Delta \eta/2}]$$

change in mass over a time step

mass fluxes through control volume faces

Scalar mass conservation equation:


$$\Delta t^{-1}(\Delta x \Delta \eta) \cdot [(\mu \phi)^{t+\Delta t} - (\mu \phi)^t] = [(\mu u \phi \Delta \eta)_{x-\Delta x/2, \eta} - (\mu u \phi \Delta \eta)_{x+\Delta x/2, \eta}] + [(\mu \omega \phi \Delta x)_{x, \eta-\Delta \eta/2} - (\mu \omega \phi \Delta x)_{x, \eta+\Delta \eta/2}]$$

change in tracer mass  
over a time step

tracer mass fluxes through  
control volume faces

## Dynamics: 5. Advection (transport) and conservation – shape preserving

### 1D advection



ARW transport is conservative,  
but not positive definite nor monotonic.  
Removal of negative q ■  
results in spurious source of q ■.

## Dynamics: 5. Advection (transport) and conservation – shape preserving

Scalar update, last RK3 step

$$(\mu \phi)^{t+\Delta t} = (\mu \phi)^t - \Delta t \sum_{i=1}^n \delta_{x_i} [f_i] \quad (1)$$

(1) Decompose flux:  $f_i = f_i^{upwind} + f_i^c$

(2) Renormalize high-order correction fluxes  $f_i^c$  such that  
solution is positive definite or monotonic:  $f_i^c = R(f_i^c)$


(3) Update scalar eqn. (1) using  $f_i = f_i^{upwind} + R(f_i^c)$

Skamarock, MWR 2006, 2241-2250

## Dynamics: 5. Advection (transport) and conservation – examples

### 1D Example: Top-Hat Advection


1D Top-hat transport  $Cr = 0.5$ , 1 revolution, 200 steps



WRF Tutorial July 2016

Bill Skamarock (skamaroc@ucar.edu)


## Dynamics: 5. Advection (transport) and conservation – examples



WRF Tutorial July 2016

Bill Skamarock (skamaroc@ucar.edu)

## Dynamics: 5. Advection (transport) and conservation – examples




WRF Tutorial July 2016

Bill Skamarock (skamaroc@ucar.edu)

## Dynamics: 5. Advection (transport) and conservation – WENO scheme

### Weighted Essentially Non-Oscillatory scheme



for  $U_{i-1/2} \geq 0$

$$flux_{i-1/2} = U_{i-1/2} \left( \frac{w_0}{\bar{w}} f_0 + \frac{w_1}{\bar{w}} f_1 + \frac{w_2}{\bar{w}} f_2 \right)$$

$$\text{where } \bar{w} = w_0 + w_1 + w_2$$

$$f_0 = \frac{1}{3} \psi_{i-3} - \frac{7}{6} \psi_{i-2} + \frac{11}{6} \psi_{i-1} \quad w_0 = \frac{0.1}{(\epsilon + \beta_0)^2}$$

$$f_1 = -\frac{1}{6} \psi_{i-2} + \frac{5}{6} \psi_{i-1} + \frac{1}{3} \psi_i \quad w_1 = \frac{0.6}{(\epsilon + \beta_1)^2}$$

$$f_2 = \frac{1}{3} \psi_{i-1} + \frac{5}{6} \psi_i - \frac{1}{6} \psi_{i+1} \quad w_2 = \frac{0.3}{(\epsilon + \beta_2)^2}$$

$$\beta_0 = \frac{13}{12} (\psi_{i-3} - 2\psi_{i-2} + \psi_{i-1})^2 + \frac{1}{4} (\psi_{i-3} - 4\psi_{i-2} + 3\psi_{i-1})^2$$

$$\beta_1 = \frac{13}{12} (\psi_{i-2} - 2\psi_{i-1} + \psi_i)^2 + \frac{1}{4} (\psi_{i-2} - 4\psi_{i-1} + 3\psi_i)^2$$

$$\beta_2 = \frac{13}{12} (\psi_{i-1} - 2\psi_i + \psi_{i+1})^2 + \frac{1}{4} (\psi_{i-1} - 4\psi_i + 3\psi_{i+1})^2$$

WRF Tutorial July 2016

Bill Skamarock (skamaroc@ucar.edu)

## Dynamics: 5. Advection (transport) and conservation – WENO scheme

### Weighted Essentially Non-Oscillatory scheme

$$\psi_i^{t+\Delta t} - \psi_i^t = -\frac{\Delta t}{\Delta x} (flux_{i+1/2} - flux_{i-1/2})$$


for  $U_{i-1/2} \geq 0$

$$flux_{i-1/2} = U_{i-1/2} \left( \frac{w_0}{w} f_0 + \frac{w_1}{w} f_1 + \frac{w_2}{w} f_2 \right)$$

Positive-definite option uses same flux-renormalization as the standard ARW transport schemes.

Can be used on momentum in addition to scalars.

## Dynamics: 5. Advection (transport) and conservation – WENO scheme



One should consider WENO for some double-moment microphysics scheme applications where noise is a problem.  
Application to momentum may not provide much benefit.

Results courtesy of Ted Mansell (NOAA/NSSL)

## Dynamics: 5. Advection (transport) and conservation

Where are the transport-scheme parameters?

The namelist.input file:  
&dynamics

`h_mom_adv_order`  
`v_mom_adv_order`  
`h_sca_adv_order`  
`v_sca_adv_order`

scheme\_order (2, 3, 4, or 5)  
defaults:  
horizontal (`h_*`) = 5  
vertical (`v_*`) = 3

`momentum_adv_opt`

= 1 standard scheme  
= 3 5<sup>th</sup> order WENO  
default: 1

`moist_adv_opt`  
`scalar_adv_opt`  
`chem_adv_opt`  
`tracer_adv_opt`  
`tkc_adv_opt`

options:  
= 1, 2, 3 : no limiter,  
positive definite (PD),  
monotonic  
= 4 : 5<sup>th</sup> order WENO  
= 5 : 5<sup>th</sup> order PD WENO

## Dynamics: 6. Time step parameters

3<sup>rd</sup> order Runge-Kutta time step  $\Delta t_{RK}$

Courant number limited, 1D:  $C_r = \frac{U\Delta t}{\Delta x} < 1.43$

Generally stable using a timestep approximately twice as large as used in a leapfrog model.

Where?

The namelist.input file:

&domains

`time_step` (integer seconds)

`time_step_fract_num`

`time_step_fract_den`



## Dynamics: 6. Time step parameters

3<sup>rd</sup> order Runge-Kutta time step  $\Delta t_{RK}$  (&domains *time\_step*)

Acoustic time step

2D horizontal Courant number limited:  $C_r = \frac{C_s \Delta \tau}{\Delta h} < \frac{1}{\sqrt{2}}$   
 $\Delta \tau_{sound} = \Delta t_{RK} / (\text{number of acoustic steps})$

Where?

The namelist.input file:

&dynamics

*time\_step\_sound* (integer)



## Dynamics: 6. Time step parameters

3<sup>rd</sup> order Runge-Kutta time step  $\Delta t_{RK}$  (&domains *time\_step*)

Acoustic time step [*&dynamics time\_step\_sound* (integer)]

Guidelines for time step

$\Delta t_{RK}$  in seconds should be about  $6 * \Delta x$  (grid size in kilometers). Larger  $\Delta t$  can be used in smaller-scale dry situations, but *time\_step\_sound* (default = 4) should increase proportionately if larger  $\Delta t$  is used.

If ARW blows up (aborts) quickly, try:

Decreasing  $\Delta t_{RK}$  (that also decreases  $\Delta t_{sound}$ ),

Or increasing *time\_step\_sound* (that decreases  $\Delta t_{sound}$  but does not change  $\Delta t_{RK}$ )

## Dynamics: 7. Filters – divergence damping

Purpose: filter acoustic modes (3-D divergence,  $D = \nabla \cdot \rho \mathbf{V}$ )

$$\left\{ \frac{\partial \rho \mathbf{V}}{\partial t} + \nabla p + \dots = \gamma'_d \nabla D \right\}$$

$$\nabla \cdot \left\{ \right\} \rightarrow \frac{\partial D}{\partial t} + \nabla^2 p + \dots = \gamma'_d \nabla^2 D$$

From the pressure equation:  $p_t \simeq c^2 D$

$$\frac{\partial \rho \mathbf{V}}{\partial t} + \nabla [p_\tau + \gamma_d (p^\tau - p^{\tau - \Delta \tau})] + \dots = 0$$

$\gamma_d = 0.1$  recommended (default) (&dynamics *smdiv*)

(Illustrated in height coordinates for simplicity)

## Dynamics: 7. Filters – time off-centering the vertical acoustic modes

Purpose: damp vertically-propagating acoustic modes

$$\frac{\partial W}{\partial t} + g \left( \mu_d - \frac{\alpha}{\alpha_d} \frac{\partial p}{\partial \eta} \right)^\tau = \dots$$

$$\frac{\partial \phi}{\partial t} - \frac{g}{\mu_d^t} \bar{W}^\tau = \dots$$

$$\overline{(\quad)}^\tau = \frac{1 + \beta}{2} \overline{(\quad)}^{\tau + \Delta \tau} + \frac{1 - \beta}{2} \overline{(\quad)}^\tau$$

Slightly forward centering the vertical pressure gradient damps 3-D divergence as demonstrated for the divergence damper

$\beta = 0.1$  recommended (default) [&dynamics *epssm*]

## Dynamics: 7. Filters – external mode filter

*Purpose: filter the external mode*

Vertically integrated horizontal divergence,  $D_h = \int_1^0 (\nabla_\eta \cdot \mu \mathbf{V}_h) d\eta$

$$\left\{ \frac{\partial \mu \mathbf{V}_h}{\partial t} + \dots = -\gamma_e \nabla_\eta D_h \right\}$$

$$\int_1^0 \nabla_\eta \cdot \left\{ \right\} d\eta \rightarrow \frac{\partial D_h}{\partial t} + \dots = \gamma_e \nabla^2 D_h$$

Continuity equation:  $\frac{\partial \mu}{\partial t} = -\nabla_\eta \cdot \mu \mathbf{V}_h - \frac{\partial \mu \dot{\eta}}{\partial \eta} = D_h$

$$\frac{\partial \mu \mathbf{V}_h}{\partial \tau} + \dots = -\gamma_e \frac{\Delta x^2}{\Delta \tau^2} \nabla_\eta (\mu^\tau - \mu^{\tau-\Delta \tau})$$

$\gamma_e = 0.01$  recommended (default) [&dynamics emdiv]

(Primarily for real-data applications)

## Dynamics: 7. Filters – vertical velocity damping

**Purpose: damp anomalously-large vertical velocities**

(usually associated with anomalous physics tendencies)

Additional term:

$$\partial_t W = \dots - \mu_d \text{sign}(W) \gamma_w (Cr - Cr_\beta)$$

$$Cr = \left| \frac{\Omega dt}{\mu d\eta} \right|$$

$Cr_\beta = 1.0$  typical value (default)

[share/module\_model\_constants.F w\_beta]

$\gamma_w = 0.3$  m/s<sup>2</sup> recommended (default)

[share/module\_model\_constants.F w\_alpha]

[&dynamics w\_damping 0 (off; default) 1 (on)]

## Dynamics: 7. Filters – 2D Smagorinsky

**2nd-Order Horizontal Mixing,  
Horizontal-Deformation-Based  $K_h$**

Purpose: mixing on horizontal coordinate surfaces  
(real-data applications) [&dynamics diff\_opt=1, km\_opt=4]

$$K_h = C_s^2 l^2 \left[ 0.25(D_{11} - D_{22})^2 + \overline{D_{12}^2}^{xy} \right]^{\frac{1}{2}}$$

where  $l = (\Delta x \Delta y)^{1/2}$

$$D_{11} = 2m^2 [\partial_x(m^{-1}u) - z_x \partial_z(m^{-1}u)]$$

$$D_{22} = 2m^2 [\partial_y(m^{-1}v) - z_y \partial_z(m^{-1}v)]$$

$$D_{12} = m^2 [\partial_y(m^{-1}u) - z_y \partial_z(m^{-1}u) + \partial_x(m^{-1}v) - z_x \partial_z(m^{-1}v)]$$

$C_s = 0.25$  (Smagorinsky coefficient, default value)

[&dynamics c\_s]

## Dynamics: 7. Filters – gravity-wave absorbing layer

**Implicit Rayleigh w Damping Layer for Split-Explicit  
Nonhydrostatic NWP Models (gravity-wave absorbing layer)**

*Modification to small time step:*

- Step horizontal momentum, continuity, and potential temperature equations to new time level:

$$\begin{matrix} U^{\tau+\Delta\tau} & \mu^{\tau+\Delta\tau} \\ \Omega^{\tau+\Delta\tau} & \Theta^{\tau+\Delta\tau} \end{matrix}$$

- Step vertical momentum and geopotential equations (implicit in the vertical):

$$W^{*\tau+\Delta\tau} \quad \phi^{*\tau+\Delta\tau}$$

- Apply implicit Rayleigh damping on  $W$  as an adjustment step:**

$$W^{\tau+\Delta\tau} = W^{*\tau+\Delta\tau} - \Delta\tau R_w(\eta) W^{\tau+\Delta\tau}$$

- Update final value of geopotential at new time level:

$$\phi^{\tau+\Delta\tau}$$

## Dynamics: 7. Filters – gravity-wave absorbing layer

Implicit Rayleigh w Damping Layer for Split-Explicit  
Nonhydrostatic NWP Models (gravity-wave absorbing layer)

$$W^{\tau+\Delta\tau} = W^{*\tau+\Delta\tau} - \Delta\tau R_w(\eta) W^{\tau+\Delta\tau}$$


$$R_w(\eta) = \begin{cases} \gamma_r \sin^2 \left[ \frac{\pi}{2} \left( 1 - \frac{z_{top}-z}{z_d} \right) \right] & \text{for } z \geq (z_{top} - z_d); \\ 0 & \text{otherwise,} \end{cases} \quad \begin{array}{l} R_w(\eta) \text{- damping rate (t}^{-1}\text{)} \\ z_d \text{- depth of the damping layer} \\ \gamma_r \text{- damping coefficient} \end{array}$$

[&dynamics damp\_opt = 3 (default = 0)]

[&dynamics damp\_coef = 0.2 (recommended, = 0. default)]

[&dynamics zdamp = 5000. ( $z_d$ (meters); default); height below  
model top where damping begins]

## Dynamics: 7. Filters – gravity-wave absorbing layer example



## Dynamics: 8. Map projections and global configuration

ARW Model: projection options

1. Cartesian geometry:  
idealized cases
2. Lambert Conformal:  
mid-latitude applications
3. Polar Stereographic:  
high-latitude applications
4. Mercator:  
low-latitude applications
5. Latitude-Longitude global, regional

Projections 1-4 are isotropic ( $m_x = m_y$ )

Latitude-longitude projection is anisotropic ( $m_x \neq m_y$ )



## Dynamics: 8. Map projections and global configuration

Global ARW – Polar filters

Converging gridlines severely limit timestep.  
The polar filter removes this limitation.

Filter procedure - Along a grid latitude circle:

1. Fourier transform variable.
2. Filter Fourier coefficients.
3. Transform back to physical space.



$$\hat{\phi}(k)_{\text{filtered}} = a(k) \hat{\phi}(k), \quad \text{for all } k$$

$$a(k) = \min \left[ 1, \max \left( 0, \left( \frac{\cos \psi}{\cos \psi_o} \right)^2 \frac{1}{\sin^2(\pi k/n)} \right) \right]$$

$k$  = dimensionless wavenumber

$\hat{\phi}(k)$  = Fourier coefficients from forward transform


$a(k)$  = filter coefficients

$\psi$  = latitude  $\psi_o$  = polar filter latitude, filter when  $|\psi| > \psi_o$

## Dynamics: 8. Map projections and global configuration

### ARW integration with polar filtering

Begin time step




End time step

Timestep limited by minimum  $\Delta x$  outside of polar-filter region.  
Monotonic and PD transport is not available for global model.

## Dynamics: 8. Map projections and global configuration

### An alternative to global ARW...

**MPAS**  
Model for Prediction Across Scales



- Global, nonhydrostatic, C-grid Voronoi mesh
- Numerics similar to WRF; WRF-NRCM physics
- No pole problems
- Variable-resolution mesh – no nested BC problems

Available at: <http://mpas-dev.github.io/>



## Dynamics: 9. Boundary condition options

### ARW Model: Boundary Condition Options

#### Lateral boundary conditions

1. Specified (Coarse grid, real-data applications).
2. Open lateral boundaries (gravity-wave radiative).
3. Symmetric lateral boundary condition (free-slip wall).
4. Periodic lateral boundary conditions.
5. Nested boundary conditions (specified).


#### Top boundary conditions

1. Constant pressure.

#### Bottom boundary conditions

1. Free slip.
2. Various B.L. implementations of surface drag, fluxes.

## Dynamics: Where are things?



### WRF ARW Tech Note

A Description of the Advanced Research WRF Version 3 (June 2008, 2012 update)  
<http://www.mmm.ucar.edu/wrf/users/pub-doc.html>