


# WRF:

## *More Runtime Options*

*Wei Wang*  
*January 2017*



# More options

---

- Some useful *runtime* options:
  - Vertical interpolation options
  - IO options
  - Base state parameters
  - Options for long simulations
  - Adaptive-time step
  - Digital filter
  - Global runs
  - Moving nest
  - TC options
  - Tracer / trajectory
  - Optional output
  - Stochastic kinetic-energy backscatter scheme (SKEB)
  - IO quilting
- Time series output (surface and profile)



# namelist.input

general namelist  
records:

`&time_control`  
`&domains`  
`&physics`  
`&dynamics`  
`&bdy_control`  
`&namelist_quilt`

specialized namelist  
records:

`&dfi_control`  
`&fdda`  
`&grib2`  
`&scm`  
`&tc`  
`&noah_mp`

Look for these in  
**`examples.namelist`**



# Vertical interpolation options (1)

---

Program **real** only, optional, &domains:

**use\_surface**: whether to use surface observations

**use\_levels\_below\_ground**: whether to use data below the ground

**lowest\_lev\_from\_sfc**: logical, whether surface data is used to fill the lowest model level values

**force\_sfc\_in\_vinterp**: number of levels to use surface data, default is 1

**extrap\_type**: how to do extrapolation: 1 - use 2 lowest levels; 2 - constant

**t\_extrap\_type** : extrapolation option for temperature: 1 - isothermal; 2 - 6.5 K/km; 3 - adiabatic



# Vertical interpolation options (2)



Program **real**, optional:

**interp\_type**: in pressure or log pressure

**lagrange\_order**: linear or quadratic

**zap\_close\_levels**:  $\Delta p$  where a non-surface pressure level is removed in vertical interpolation

related namelists: **examples.namelist**




# IO Control (1)

---

## History output control in `&time_control`

<code>history_interval:</code>	used often, unit in <u>minutes</u>
<code>history_interval_h:</code>	history output interval in hours
<code>history_interval_s:</code>	history output interval in seconds
<code>history_begin_h:</code>	history output beginning time in hours
<code>history_begin_d:</code>	history output beginning time in days

Look for listing in `Registry/`  
`registry.io_boilerplate`



# IO Control (2)

---

## Optional history output in `&time_control`


### 1. Change Registry.EM and **recompile**:

```
state integer rainc ij misc 1 - h03 "RAINC" ""  
"ACCUMULATED TOTAL CUMULUS PRECIPITATION"
```

```
state integer rainnc ij misc 1 - h03 "RAINC" ""  
"ACCUMULATED TOTAL GRID SCALE PRECIPITATION"
```

### 2. Edit namelist.input to output these variables:

```
auxhist3_outname = "rainfall_d<domain>"  
auxhist3_interval = 10, 10,  
frames_per_auxhist3 = 1000, 1000,  
io_form_auxhist3 = 2
```



# IO Control (3)

Starting in V3.2, there is an alternative to add/remove additional output at **runtime** (state variables in Registry only)

1. new namelists in `&time_control`:

```
iofields_filename(max_dom) = 'my_output.txt',  
ignore_iofields_warning = .true.
```

2. prepare a text file ( `'my_output.txt'` ) to select io fields:

```
+:h:3:rainc,rainnc    ← syntax in the file
```

3. set other namelists under `&time_control`:

```
auxhist3_outname = "rainfall_d<domain>"  
auxhist3_interval = 10, 10,  
frames_per_auxhist3 = 1000, 1000,  
io_form_auxhist3 = 2
```

See **'Run-Time IO'** section in Chapter 5, User's Guide





# Base State Parameters

---

The following could be varied:

**base\_temp**


Base state surface temperature

**iso\_temp**

Base state stratosphere temperature

**base\_pres\_strat**

Pressure at which the stratosphere temperature lapse rate changes (since 3.6.1)



Help to improve simulations when model top is higher than 20 km (~ 50 mb)



# Options for long simulations (1)

---

Lower boundary update control: allow SST, seaice, monthly vegetation fraction, and albedo to be updated regularly during a model run:

**sst\_update:** 0 – no update

1 – update all above fields

Set before running **real.exe**, and this will create additional output files: **wrflowinp\_d01**, **wrflowinp\_d02**, ..

Other namelists required in **&time\_control**:

**auxinput4\_inname** = “wrflowinp\_d<domain>”

**auxinput4\_interval** = 360, 360,

**io\_form\_auxinput4** = 2 (netCDF)

See ‘**Using sst\_update Option**’ in Chapter 5, User’s Guide



# Options for long simulations (2)

---

<code>sst_skin</code>	diurnal water temp update
<code>tmn_update</code>	deep soil temp update, used with lagday
<code>lagday</code>	averaging time in days
<code>bucket_mm</code>	bucket reset value for rainfall (e.g. <code>rainc=i_rainc*bucket_mm+rainc</code> )
<code>bucket_j</code>	bucket reset value for radiation fluxes
<code>spec_exp</code>	exponential multiplier for boundary zone ramping (set in <i>real</i> ). Usually used with wider boundary zone




# Adaptive time steps (1)

- Adaptive-time-step is a way to maximize the model time step while keeping the model numerically stable.
- New in V3. Good to use for real-time run.
- May not work in combination with other options.

Also see ‘**Using Adaptive Time Stepping**’  
section in Chapter 5, UG



# Adaptive time steps (2): an example



On average, forecasts finish in 60 min (50-73min) as compared to 79 min standard runtime



# Adaptive time steps (3)

Namelist control: `&domains` \* **USE WITH CARE**

`use_adaptive_time_step`

logical switch

`step_to_output_time`

whether to write at exact history output times

`target_cfl`

maximum cfl allowed (1.2)

`max_step_increase_pct`

percentage of time step increase each time; set to 5, 51, 51 (larger value for nest)

`starting_time_step`

in seconds; e.g. set to  $4 \cdot DX$

`max_time_step`

in seconds; e.g. set to  $8 \cdot DX$

`min_time_step`

in seconds; e.g. set to  $4 \cdot DX$




# Digital filter initialization (1)

---

Digital filter initialization is a simple way to remove initial model imbalance:

- May be introduced by simple interpolation, different topography, or by objective analysis, or data assimilation
- It may generate spurious gravity waves in the early simulation hours, which could cause erroneous precipitation, numerical instability and degrade subsequent data assimilation
- Useful for short-range (1-6 h) forecast



# Digital filter initialization (2)

---

## Using DFI

- can construct consistent model fields which do not exist in the initial conditions, e.g. vertical motion, cloud variables
- may reduce the spin-up problem in early simulation hours
- Useful if the first few hours of forecast is the interest

DFI is done after program **real**, or data-assimilation step, just before model integration




See ‘**Using Digital Filter Initialization**’, Chap 5, UG.

---




# Digital filter initialization (3)



# Digital filter initialization (4)


**DFL:**

(Lynch and Huang, 1994)




**DDFI:**

(Huang and Lynch, 1993)



**TDFI:**

(Lynch and Huang, 1994)



# Digital filter initialization (5)

---

Namelist control: **&dfi**

**dfi\_opt**: dfi options: 0: no DFI; 1: DFL; 2: DDFI; 3: TDFI (recommended)

**dfi\_nfilter**: filter options 0 - 8, recommended: 7

**dfi\_cutoff\_seconds** : cutoff period

**dfi\_write\_filtered\_input** : whether to write filtered IC

**dfi\_bckstop\_\*** : stop time for backward integration

**dfi\_fwdstop\_\*** : stop time for forward integration

related namelists: **examples.namelist**



To get pressure tendency data, set **diag\_print=1** or **2**

# Global application

---

- Setup mostly done in WPS:

`map_proj = 'lat-lon'`

`e_we, e_sn`: `geogrid` will compute dx, dy

See template `'namelist.wps.global'`

- Requires only one-time period data
- In the model stage:

`fft_filter_lat`: default value is 45 degrees

Caution: some options do not work, or have not been tested with global domain. Start with template `'namelist.input.global'`



See **'Global Run'** section, Chap 5, UG

---

# Automatic moving nest options

---

Tropical cyclone / typhoon / hurricane applications:

**vortex\_interval:** time interval when vortex location is estimated

**max\_vortex\_speed:** used to compute the search radius for vortex location

**corral\_dist:** how far the vortex can move near the parent domain boundary (number of grids)

**track\_level:** e.g. 700 or 500 mb

**time\_to\_move:** hold nests still until this time





See ‘**Moving Nested Run**’, Chap 5, UG

---

# TC options (1)

**isftcflx:** alternative  $C_d$  (Donelan) and  $C_k$  ( $=2$ , Garratt) formulation for TC application



## TC options (2)

**sf\_ocean\_physics=1:** simple ocean mixed layer


**oml\_hml0:** initial ocean mixed layer depth

**oml\_gamma:** lapse rate in deep water

**oml\_relaxation\_time:** time scale to relax ocean temperature back to initial value

The ocean mixed layer model can also be initialized with real-data, e.g. HYCOM. More info can be found at

[http://www2.mmm.ucar.edu/wrf/users/hurricanes/wrf\\_ahw.html](http://www2.mmm.ucar.edu/wrf/users/hurricanes/wrf_ahw.html)



# TC options (3)

**sf\_ocean\_physics = 2:**

3D Price-Weller-Pinkel (PWP) ocean model based on Price et al. (1994). It has full ocean process (e.g. advection, pressure-gradient force, and mixing). It doesn't have ocean bathymetry (or ocean depth). Only simple initialization is provided in Version 3.5.





# tracer option

Add the following in `&dynamics` to activate tracer option (default no. is 8: with array names `tr17_1`, `tr17_2`, ..., `tr17_8`):

```
tracer_opt = 2,
```

One would need some way to initialize the tracer. A simple initialization can be found in program real (`dyn_em/module_initialize_real.F`)



# trajectory option

Add the following in `&physics` to activate trajectory option:

```
traj_opt = 1,
```

And set the number of trajectories in `&domains`:

```
num_traj = 25, (default value)
```

Output: `traj_i(num_traj), traj_j, traj_k,  
traj_lat, traj_long`

To change initial launch points, edit code in  
initialization program `real.exe (dyn_em/  
module_initialize_real.F)`



# Stochastic kinetic-energy backscatter scheme

---

This is a way to stochastically perturb forecasts.

**stoch\_force\_opt:** = 1, activate the scheme

**nens:** = N, an integer that controls the random number stream; a different integer will give a differently perturbed forecast

**perturb\_bdy:** = 1, use SKEB pattern; = 2, use user-provided pattern (new in 3.5)

Also see ‘**Option to stochastically perturb forecasts**’ section in Chap 5, UG

Also see <http://www.cgd.ucar.edu/~berner/skebs.html>



# Additional Output Option (1)

---

`prec_acc_dt = 60.:`

Output precipitation in a time interval (e.g. 60 min):

`PREC_ACC_C`, for convective rain

`PREC_ACC_NC`, for explicit rain

`SNOW_ACC_NC`, for explicit snow

(May not suitable for use in long runs)



# Additional Output Option (2)

---

*Since V3.4.1:*

`&diags`

`p_lev_diag = 1.`

`num_press_levels = 4,`

`press_levels = 85000,70000,50000,20000`

Output a few met fields on pressure levels :

`U_PL, V_PL, S_PL, T_PL, TD_PL, RH_PL, GHT_PL,`

Output goes to auxiliary stream 23, so need to set

`auxhist23_outname, io_form_auxhist23,`

`auxhist23_interval, frames_per_auxhist23`



# Additional Output Option (3)

---

`output_diagnostics = 1:`

output max, min, time of max and min, mean value, standard deviation of the mean for 8 surface variables (T2, Q2, TSK, U10, V10, 10 m wind speed, RAINCV, and RAINNCV [time step rain])

`auxhist3_outname = "wrfxtrm_d<domain>_<date>"`

`io_form_auxhist3 = 2`

`auxhist3_interval = 1440, 1440,`

`frame_per_auxhist3 = 10, 10,`



# Additional Output Option (4)

---

`nwp_diagnostics = 1:`

Output max 10 m wind speed, max helicity in 2 – 5 km layer, max w in updraft and downdraft below 400 mb, mean w in 2 – 5 km layer, and max column graupel in a time window between history output times.

Data goes to history file.



# Additional Output Option (5)

---

`do_radar_ref = 1:`

Compute radar reflectivity using parameters used by different microphysics. Works for options mp\_physics = 2,4,6,7,8,10,14,16. Option 9, NSSL mp also produce radar reflectivity output.

Data goes to history file.





# Additional Output Option (6)

---

`do_avgflx_em = 1:`

output history-time-averaged, column-pressure-coupled u, v and w:

`AVGFLX_RUM, AVGFLX_RVM, AVGFLX_RWM`

– useful for driving downstream transport model



# Additional Output Option (7) (*extra*)

`afwa*_opt = 1:` (with sub-options)

output over 60 diagnostic variables to history file  
(for example, MSLP, precipitable water, cloud  
cover, etc.)

See Registry/registry.afwa for full listing.

Data goes to history as well as auxhist2 file.



# IO quilting: &namelist\_quilt

---

## Parallel I/O control:

**nio\_tasks\_per\_group** (>0) : allow IO to be done on separate processors. Performance improvement for large domain runs. A value of 2 to 4 works well.

**io\_groups** (>1) : number of I/O streams that the quilting applies.

See ‘**Using IO Quilting**’ section, Chap 5, UG

Other ways to improve IO: 1) p-netCDF; 2) use netCDF4 compression option; 3) use io\_form\_history=102 to output patches of data



# Time Series Output (1)

- It is a special output in text format with file name like  
*prefix.d<domain>.TS*
- It outputs 14 surface variables at every time step:  
e.g. 10 m u/v, 2 m T/qv, precipitation, radiation fluxes, surface fluxes
- One file per location (e.g. at weather station), per domain



## Time Series Output (2)

- It also outputs profiles of U, V, Th, Qv, PH (levels set by `max_ts_level`, default 15):

*prefix.d<domain>.UU*


*prefix.d<domain>.VV*

*prefix.d<domain>.TH*

*prefix.d<domain>.QV*

*prefix.d<domain>.PH*

- One file per location (e.g. at weather station), per domain.




# Time Series Output (3)

- Not a namelist option
- If output more than 5 locations, use namelist **max\_ts\_locs**
- Depends the presence of a file called '**tslist**' (a sample of the file is available in **WRFV3/run/**)

```
#-----#  
# 24 characters for name | pfx | LAT | LON |  
#-----#  
Cape Hallett          hallt -72.330  170.250  
McMurdo Station      mcm   -77.851  166.713
```


- This file provides a list of locations where you would like to output time series
- More information in **run/README.tslist** and '**Output Time Series**' section, Chapter 5, UG



# Time Series Output (4)

## Content in hallt.d01.TS:

```
Cape Hallett          1  1 hallt ( 36.710, -79.000) ( 41,  38)
( 36.600, -79.142) 159.6 meters
1      0.050000      1  41    38      275.47397      0.00288
3.52110      -2.34275  99988.76563      244.81276
0.00000      -29.94841      4.09765      273.90295      278.20197
0.00000      0.00000      0.00000
1      0.100000      1  41    38      275.56287      0.00282
3.14414      -2.05875  99956.98438      244.81276
0.00000      -25.64095      4.18446      273.78323      278.18314
0.00000      0.00000      0.00000
```



# Recommended

---

Start with the **namelist template** in a particular test directory, and the options specified in the file, and make modifications.

Chapter 5 of ARW User's Guide, pages 5-34 – 5-36: examples for various applications.

For special applications in ARW, look for related namelists in the file *examples.namelist* in *test/em\_real/* directory.

For more information on global extension, DFI and adaptive time step, read Tech Note, and User's Guide.

