NESTING IN WRF

Kelly Werner & Wei Wang
January 2018

What is a nest?

- A *finer-resolution* domain embedded in a coarser resolution domain, and run together with the coarser resolution domain
- Enables running at a higher-resolution without:
  - Uniformly high-resolution over a large domain – VERY expensive
  - High resolution for a very small domain, with mismatched time and spatial lateral boundary conditions

What is a nest?

- Covers a portion of the parent domain, and is fully contained by the parent domain
- Driven along its lateral boundaries by the parent domain
- May feedback the computed values back to the parent domain



When Should I Use Nests?



When Should I Use Nests?



When Should I Use Nests?

- Need to simulate localized phenomena: convection, topography, landuse-forced, etc.
  - What resolution is necessary to resolve what you are interested in?
  - Input data resolution is too coarse by more than a factor of 5-10x
  - Would like to provide better boundary conditions for the area of interest
    - BC's for external sources are typically 3-6 hours and do not have tendencies for all predicted fields
  - Computing resources not available for uniform coverage

Types of Nesting

- Using a single input domain (met_em.d01*)
  - No met_em.d02* files are used
  - All fields are interpolated from the model coarse grid
  - Only recommended if nest is over the ocean
- Using multiple input domains
  - Each domain contains full input data files (including topography, landuse, etc.)
- Specified move
  - Must specify every move
  - Can use, but tedious to set-up
- Automatic move
  - Build WRF with "3=vortex following"
  - Only for tropical cyclone tracking
  - Expensive for single large nest
- ndown.exe
  - Use coarser WRF model output to drive finer resolution domains (i.e. 'downscaling')
  - If you have run a long coarse domain simulation (years) and later decide you want to have a nest with higher resolution.

Types of Nesting

One-way/two-way nesting

- Determined by the namelist parameter "feedback"
  - **feedback = 0 (turned off/one-way)**

Lateral boundary conditions are fed to the nest, from the parent.



Types of Nesting

One-way/**two-way nesting**

- Determined by the namelist parameter “feedback”
  - **feedback = 1 (turned on/two-way)**

(1) Lateral boundary conditions are fed to the nest, from the parent.

(2) Child values are averaged, and then sent back to parent to overwrite value at corresponding grid point



Masked Feedback



Single grid value feedback for categorical and masked data

Nests that are OK





Nests that are NOT OK



Child domains *may not* have overlapping points in the parent domain (possible if Feedback is off).

Nests that are NOT OK



Nests that are NOT OK



Nesting Set-up and Run

Compiling for Nesting (WRF)

```
------------------------------------------------------------------------
Please select from among the following Darwin ARCH options:

  1. (serial)   2. (smpar)   3. (dmpar)   4. (dm+sm)   PGI (pgf90/pgcc)
  5. (serial)   6. (smpar)   7. (dmpar)   8. (dm+sm)   INTEL (ifort/icc)
  9. (serial)  10. (smpar)  11. (dmpar)  12. (dm+sm)   INTEL (ifort/clang)
 13. (serial)               14. (dmpar)                GNU (g95/gcc)
 15. (serial)  16. (smpar)  17. (dmpar)  18. (dm+sm)   GNU (gfortran/gcc)
 19. (serial)  20. (smpar)  21. (dmpar)  22. (dm+sm)   GNU (gfortran/clang)
 23. (serial)               24. (dmpar)                IBM (xlf90_r/cc)
 25. (serial)  26. (smpar)  27. (dmpar)  28. (dm+sm)   PGI (pgf90/pgcc): -f90=pgf90

Enter selection [1-28] : 9
------------------------------------------------------------------------
Compile for nesting? (0=no nesting, 1=basic, 2=preset moves, 3=vortex following) [default 0]:
```

Compile with nesting option (1=basic)

*Note: Unless compiling for a moving nest, or 2D idealized case, there's no reason to not always choose "basic." It takes no longer to build.

namelist.wps - WPS

namelist.*wps* set-up: *&share*

To edit the namelist.wps file, make sure you are in the WPS/ directory

```
&share
 wrf_core = 'ARW',
 max_dom = 2,
 start_date = '2012-01-27_00:00:00', '2012-01-27_00:00:00'
 end_date = '2012-01-28_00:00:00', 2012-01-27_00:00:00'
 interval_seconds = 21600
 io_form_geogrid = 2,
/
```

real.exe program only requires initial time for fine domain (unless doing nudging or SST-update in the nest)

Make sure to edit start/end dates for all domains!

namelist.*wps* set-up: *&geogrid*

```
&geogrid

 parent_id         =  1,      1,
 parent_grid_ratio =  1,      3,
 i_parent_start    =  1,     70,
 j_parent_start    =  1,     67,

 e_we              = 175,   181,
 e_sn              = 145,   181,
 geog_data_res     = 'default', 'default',


 dx                = 30000,
 dy                = 30000,
 map_proj     = 'lambert',
 ref_lat      = 37.0,
 ref_lon      = -97.0,
 truelat1     = 45.0,
 truelat2     = 30.0,
 stand_lon    = -97.0,
 geog_data_path = '/data/static/geog/'
/
```

Used for nesting purposes
- What is the grid ratio for each nest?
- Where is it located inside its parent?
- parent_grid_ratio: integer ratio required

Domain sizes: How many grid points does each domain have?

namelist.*wps* set-up: *&geogrid*

```
&geogrid

 parent_id         =  1,      1,
 parent_grid_ratio =  1,      3,
 i_parent_start    =  1,     70,
 j_parent_start    =  1,     67,

 e_we              = 175,   181,
 e_sn              = 145,   181,
 geog_data_res     = 'default', 'default',


 dx                = 30000,
 dy                = 30000,
 map_proj     = 'lambert',
 ref_lat      = 37.0,
 ref_lon      = -97.0,
 truelat1     = 45.0,
 truelat2     = 30.0,
 stand_lon    = -97.0,
 geog_data_path = '/data/static/geog/'
/
```

parent_id:
The domain # of the nest's parent



parent_id = 1, 1, 2, 1

namelist.*wps* set-up: *&geogrid*

```
&geogrid

 parent_id         =  1,      1,
 parent_grid_ratio =  1,      3,
 i_parent_start    =  1,     70,
 j_parent_start    =  1,     67,

 e_we              = 175,   181,
 e_sn              = 145,   181,
 geog_data_res     = 'default', 'default',


 dx                = 30000,
 dy                = 30000,
 map_proj     = 'lambert',
 ref_lat      = 37.0,
 ref_lon      = -97.0,
 truelat1     = 45.0,
 truelat2     = 30.0,
 stand_lon    = -97.0,
 geog_data_path = '/data/static/geog/'
/
```

parent_grid_ratio:
recommended ratios are 3:1 or 5:1 (odd ratios, less than 7)

i/j_parent_start:



Feedback 3:1 Ratio

When using feedback, conditions are fed back to the parent domain from the child along the rows and columns, and at the mass points (center)

U: east-west velocities
V: south-north velocities
Θ: all other meteorological data

➡ Averaging is performed



WRF Parent-nest Domain Overlap



i_parent_start
j_parent_start

- The nested domain can be placed *anywhere* within the parent domain and the nested grid cells will exactly overlap the parent cells at the coincident cell boundaries
- Coincident parent/nest grid points eliminate the need for complex, generalized remapping calculations, and enhances model performance and portability.

namelist.*wps* set-up: *&geogrid*

```
&geogrid

 parent_id         =  1,      1,
 parent_grid_ratio =  1,      3,
 i_parent_start    =  1,     70,
 j_parent_start    =  1,     67,

 e_we              = 175,   181,
 e_sn              = 145,   181,
 geog_data_res     = 'default', 'default',


 dx                = 30000,
 dy                = 30000,
 map_proj     = 'lambert',
 ref_lat      = 37.0,
 ref_lon      = -97.0,
 truelat1     = 45.0,
 truelat2     = 30.0,
 stand_lon    = -97.0,
 geog_data_path = '/data/static/geog/'
/
```

e_we and e_sn:
Each domain's full west-east and south-north dimensions



Notes:
- Domains should be no smaller than about 100x100
- Avoid placing any boundaries over complex terrain
- Keep nest away from coarse domain

namelist.*wps* set-up: *&geogrid*

```
&geogrid

 parent_id         =  1,      1,
 parent_grid_ratio =  1,      3,
 i_parent_start    =  1,     70,
 j_parent_start    =  1,     67,

 e_we              = 175,   181,
 e_sn              = 145,   181,
 geog_data_res     = 'default', 'default',


 dx                = 30000,
 dy                = 30000,
 map_proj     = 'lambert',
 ref_lat      = 37.0,
 ref_lon      = -97.0,
 truelat1     = 45.0,
 truelat2     = 30.0,
 stand_lon    = -97.0,
 geog_data_path = '/data/static/geog/'
/
```

Minimum distance between nest boundary and parent boundary:
- 4 grid cells
- need MUCH larger buffer zone



- Good practice to have ~1/3 of coarse-grid surrounding each side of nest
- Nest can be placed a bit downstream of the inflow boundary

namelist.*wps* set-up: *&geogrid*

```
&geogrid

 parent_id         =  1,      1,
 parent_grid_ratio =  1,      3,
 i_parent_start    =  1,     70,
 j_parent_start    =  1,     67,

 e_we              = 175,   181,
 e_sn              = 145,   181,
 geog_data_res     = 'default', 'default',


 dx                = 30000,
 dy                = 30000,
 map_proj     = 'lambert',
 ref_lat      = 37.0,
 ref_lon      = -97.0,
 truelat1     = 45.0,
 truelat2     = 30.0,
 stand_lon    = -97.0,
 geog_data_path = '/data/static/geog/'
/
```

dx and dy:
Only need the coarse domain resolution. The geogrid program calculates the nest resolution(s) using the "parent_grid_ratio"

***Note:**
No changes need to be made to the &ungrib and &metgrid namelists records for nesting purposes

namelist.input (WRFV3)

namelist.*input* set-up: *&time_control*

```
&time_control
 run_days                 = 0,
 run_hours                = 24,
 run_minutes              = 0,
 run_seconds              = 0,
 start_year               = 2012, 2012,   2012,
 start_month              = 01,   01,     01,
 start_day                = 27,   27,     27,
 start_hour               = 00,   00,     00,
 start_minute             = 00,   00,     00,
 start_second             = 00,   00,     00,
 end_year                 = 2012, 2012,   2012,
 end_month                = 01,   01,     01,
 end_day                  = 28,   28,     28,
 end_hour                 = 00,   00,     00,
 end_minute               = 00,   00,     00,
 end_second               = 00,   00,     00,
 interval_seconds         = 10800
 input_from_file          = .true.,.true.,  true.
 history_interval         = 360,  60,     60
 frames_per_outfile       = 1000, 1,      1
 restart                  = .false.
 restart_interval         = 180
 io_form_history          = 2
 io_form_restart          = 2
```

** To edit the namelist.input file, make sure you are in the *WRFV3/test/em_real/* (or *WRFV3/run/*) directory

start/end date/times:
These values *typically* will be the same for all domains

history_interval:
May choose to have more frequent output time for nests

frames_per_outfile:
May choose to have all history outputs in a single file, or in multiple files
- to display geographic boundaries in newer verions of ncview, it's necessary to have 1 file per time period.

namelist.*input* set-up: *&domains*

```
&domains
time_step                = 180,
time_step_fract_num      = 0,
time_step_fract_den      = 1,
max_dom                  = 2,
e_we                     = 175,   181,   94,
e_sn                     = 145,   181,   91,
e_vert                   = 36,    36,    36,
p_top_requested          = 5000,
num_metgrid_levels       = 32,
num_metgrid_soil_levels  = 4,
dx                       = 30000, 10000, 3333.33,
dy                       = 30000, 10000, 3333.33,
grid_id                  = 1,     2,     3,
parent_id                = 0,     1,     2,
i_parent_start           = 1,     70,    30,
j_parent_start           = 1,     67,    30,
parent_grid_ratio        = 1,     3,     3,
parent_time_step_ratio   = 1,     3,     3,
feedback                 = 1,
smooth_option            = 0
/
```

max_dom:
Activate nests - # of domains to run

e_we and e_sn:
should match namelist.wps values

e_vert:
All columns usually have the same value

dx/dy:
must set values for each domain.
make sure values correspond with "parent_grid_ratio"
- for non-integer grid resolutions, use at least two decimal places

namelist.*input* set-up: *&domains*

```
&domains
.....
grid_id                  = 1,     2,     3,
parent_id                = 0,     1,     2,
i_parent_start           = 1,     70,    30,
j_parent_start           = 1,     67,    30,
parent_grid_ratio        = 1,     3,     3,
parent_time_step_ratio   = 1,     3,     3,
feedback                 = 1
smooth_option            = 0
/
```

All must be set to the same values used in namelist.wps

feedback:
Whether a nest will overwrite parent results
- 2-way nesting: feedback = 1
- 1-way nesting: feedback = 0

parent_time_step_ratio:
See next slide!

Nested 3:1 Time Step Ratio

- Example: 3-domain nested run
  - D01: a single 3 min dt
  - D02: a single 1 min dt
  - D03: 20 second intervals, up to 1 min





namelist.*input* set-up: *&physics*

- You should use the same physics options for all domains for all schemes
  - **Exceptions**:
    - cumulus_scheme (cu_physics): may need to be turned off for a nest that has a grid distance of only a few kilometers
    - may turn off PBL scheme for resolutions close to 100 m
- Use same values for physics calling frequency parameters (for each domain)
  - radt: radiation time step
  - bldt: boundary layer time step
  - cudt: cumulus scheme time step

Computationally inexpensive – no reason to not always set to zero (run every time step);
NOTE: radt=15 => run radiation every 15 min

Nesting in real.exe

- *real* program reads & processes multiple domain input files from *metgrid* (met_em_d0*)
- *real* program does vertical interpolation only
- There are no consistency check between domains (this is handled in the feedback step for the WRF model)
- *real.exe* must be re-run if you make changes to:
  - Date/time
  - Domain – size, location, quantity
  - A number of physics options (those related to input fields)
  - Input data

Where do I start?

- Always start with a *namelist* template provided in the WRFV3/test/em_real (or WRFV3/run/) directory
- Use documents/websites to guide your namelist modifications
  - WRFV3/run/*README.namelist*
  - WRFV3/test/em_real/*examples.namelist*
  - Users' Guide, Chapter 5
    - http://www2.mmm.ucar.edu/wrf/users/docs/user_guide_V3.9/users_guide_chap5.htm
  - Namelist Best Practice web pages:
    - WPS: http://www2.mmm.ucar.edu/wrf/users/namelist_best_prac_wps.html
    - WRFV3: http://www2.mmm.ucar.edu/wrf/users/namelist_best_prac_wrf.html
- Not all namelist options are domain dependent. If in doubt:
  - Check WRFV3/Registry/*Registry.EM_COMMON* or *registry.io_boilerplate* (grep for parameter names)
  - Check WRFV3/run/*README.namelist* (grep for parameter names)
  - Rule of thumb: If default namelist only has 1 column, don't add values for other columns!

Steps to run with a nest

- WPS: Identical to single domain run:
  1) Make sure you are in the WPS/ directory
  2) Make necessary changes to the *namelist.wps* file
  3) Run geogrid.exe, ungrib.exe, and metgrid.exe

```
./geogrid.exe
./ungrib.exe
./metgrid.exe
```

- WRFV3: Identical to single domain run:
  1) Make sure you are in the *WRFV3/test/em_real* (or *WRFV3/run/) directory*
  2) Move or link WPS output files (*met_em.d0**) to your running directory

```
ln -sf ../../../WPS/met_em* .
```

  3) Edit *namelist.input* file for the appropriate grid and times of the case
  4) Run initialization program (assuming a dmpar compile):

```
mpirun -np n ./real.exe
```

- "n": number of processors used

  1) Run model executable (assuming a dmpar compile):

```
mpirun -np n ./wrf.exe
```

Successful *real.exe* Run

- If *real.exe* was successful, you should see this at the end of your rsl.error.0000 file (assuming a dmpar compile):
  - `tail rsl.error.0000`
  - SUCCESS COMPLETE REAL_EM INIT
- You should have these files in your running directory:
  - wrfbdy_d01 :
    - Lateral boundary data for all times (domain 01 only)
  - wrfinput_d01, wrfinput_d02, ….
    - Single time-level data at the model's start time (for all domains)
    - 1 file per domain

Successful *wrf.exe* Run

- If *wrf.exe* was successful, you should see this at the end of your rsl.error.0000 file (assuming a dmpar compile):
  - `tail rsl.error.0000`
  - SUCCESS COMPLETE WRF
- You should have these files in your running directory:
  - wrfout_d01_2005-08-28_00:00:00
  - wrfout_d02_2005-08-28_00:00:00
    - One for each domain, for each history time (depending on how you set 'frames_per_outfile')
  - wrfrst_d01_2005-08-28_00:00:00
  - wrfrst_d02_2005-08-28_00:00:00
    - If "restart_interval" is less than or equal to the integration time

Summary

- Decide what is the best strategy to do the simulation
- If nesting is required, design your nest configuration
  - Design the coarse domain first
  - Determine the beginning and ending indices of the nest on the coarse domain
- Choose the appropriate nesting strategy:
  - one-way, two-way, or one-way via *ndown*

Questions?