


# REAL

## Description of General Functions

Dave Gill

[gill@ucar.edu](mailto:gill@ucar.edu)



## Real program in a nutshell

- Function
- Standard input variables
- Base State
- Standard generated output
- Vertical interpolation
- Soil level interpolation

## Function

- The WRF model pre-processor is **real.exe**
- The real.exe program is available **serial** or **DM parallel** (primarily for aggregate memory purposes, as opposed to timing performance)
- This program is automatically generated when the model is built and the requested use is for a real data case
- The real.exe program takes data **from WPS** and transform the data **for WRF**
- Similar to the ARW idealized data pre-processor, real.exe is tightly coupled to the WRF model through the **Registry**

## Function

- **3D forecast** or simulation
- **Meteorological input** data that primarily originated from a previous forecast or analysis, probably via the WPS package
- Anticipated **utilization of physics** packages for microphysics, surface conditions, radiation, convection, and boundary layer (maybe usage of nudging capabilities)

## Function

- A non-Cartesian **projected domain**
  - Lambert conformal, Mercator, polar stereographic, rotated latitude/longitude (global or regional)
- Selection of **realistic static fields** of topography, land use, vegetation, and soil category data
- Requirement of **time dependent** lateral boundary conditions for a regional forecast

## Function

- Generation of **diagnostics** necessary for assumed WRF model input
- Input field **adjustment** for consistency of static and time dependent fields (land mask with soil temperature, etc.)
- ARW: computation of **reference** and **perturbation** fields
- Generation of **initial** state for each of the requested domains
- Creation of a **lateral boundary file** for the most coarse domain
- **Vertical interpolation** for 3d meteorological fields and for sub-surface soil data

## Function

- **Run-time options**
  - specified in the Fortran namelist file (namelist.input for real and WRF)
- **Compile-time options**
  - Changes inside of the source code
  - Compiler flags
  - CPP ifdefs
  - Modifications to the Registry file

## Standard Input Variables

- The metgrid program typically provides meteorological data to the real program.
- **Coordinate:**
  - The real program is able to input and correctly process any **strictly monotonic** vertical coordinate
    - Isobaric: OK
    - Sigma: OK
    - Hybrid: OK

## Standard Input Variables

- The metgrid program typically provides meteorological data to the real program.
- **Mandatory:**
  - 3d and surface: horizontal winds, temperature, relative humidity, geopotential height
  - 3d soil: soil temperature
  - 2d fields: surface pressure, sea-level pressure, land mask
- **Optional** (but desirable):
  - 3d soil: soil moisture
  - 2d fields: topography elevation of input data, SST, sea-ice, skin temperature


## Base State

- Several of the mass-point fields are **separated** into a time-independent **base state** (also called a reference state) and a **perturbation** from the base state
- The base state fields are only functions of the **topography** and a few user-selectable constants
- If the **topography changes**, such as with a moving nest, the base state fields are modified
- **Feedback** for 2-way nesting also impacts base state fields through topographic averaging – **inside of the WRF model**
- No base state computations are required **prior to the real program**


## Hybrid Vertical Coordinate

- New in WRF v3.9 is the capability to have a hybrid vertical coordinate: a terrain following coordinate near the surface and relaxing to isobaric surfaces aloft
- A compile-time option is required:  
**configure -hyb**
- A run-time option is required:  
**&dynamics**  
**hybrid\_opt = 2**  
**/**


## TERRAIN FOLLOWING Vertical Coordinate System



### ISOBARIC Vertical Coordinate System




### HYBRID Vertical Coordinate System




### Standard Generated Output

- For regional forecasts, the real program generates both an initial (*wrfinput\_d01*) and a lateral boundary (*wrfbdy\_d01*)
- The boundary file is not required for *global forecasts* with ARW (look at MPAS for global simulations)
- The *initial condition* file contains a *single time period* of data
- These files contain data used directly by the WRF model
- The initial condition file may be ingested by the *WRFDA* code (referred to as a *cold-start*)
- If *n* times were processed with WPS and real, the lateral boundary file contains *n-1* time slices


### Lateral Boundary Condition Times



## Lateral Boundary Condition Times



## Real-Data Lateral Boundary Condition: Location of Specified and Relaxation Zones





## Vertical Interpolation

- A number of vertical interpolation options are available to users
- The options can have a significant impact on the initial conditions passed to the model
- More information is contained in the info file **README.namelist** in the **run** directory
- Options are located in the **&domains** namelist record of **namelist.input**



## Vertical Interpolation

- Impact: *Expected region of changes*
- *Non-standard setting*
- Which level is being viewed
- Topography and domain for difference plots, 160x140, 4 km, input = 40 km NAM





## Vertical Interpolation

- Impact: few lowest levels only
  - force\_sfc\_in\_vinterp = 0
  - $\eta$  level 1
- 
- Theta (-8 K blue, 0 K yellow)
  - U (-3 m/s blue, 2 m/s red)





## Vertical Interpolation

- Impact: few lowest levels only
  - force\_sfc\_in\_vinterp = 6
  - $\eta$  level 4
- 
- Theta (0 K blue, 10 K red)
  - U (-5 m/s blue, 6 m/s red)





## Vertical Interpolation

- Impact: above first 4 levels, most near tropopause
  - lagrange\_order = 2
  - $\eta$  level TOP
- 
- Theta (0.7 K blue, 1.6 K red)
  - U (0.4 m/s blue, 1.4 m/s red)



## Vertical Interpolation


- Impact: lowest level only
  - lowest\_lev\_from\_sfc = T
  - $\eta$  level 1
- 
- Theta (-10 K blue, 8 K red)
  - U (-3 m/s blue, 7 m/s red)







## Vertical Interpolation

- Impact: outer few rows and column, amplitude damps upward
- smooth\_cg\_topo = T
- $\eta$  level 1
- Theta (-10 K blue, 9 K red)
- U (-6 m/s blue, 6 m/s red)



## Vertical Interpolation

- Impact: lowest few levels
- use\_surface = F
- $\eta$  level 1
- Theta (-11 K blue, 0 K red)
- U (-3 m/s blue, 4 m/s red)



## Vertical Interpolation

Make sure input data is vertically *ordered* as expected

Input 3-D pressure and T, topo, Z, moisture used to compute total *surface pressure*

Compute target *vertical coordinate* using normalized dry column pressure

The *eta surfaces* may be computed or selected

Vertically interpolate input fields in pressure to the  $\eta$  surfaces in dry pressure: default all variables linear in  $\log(\text{pressure})$

## Vertical Interpolation

- Select reasonable  $\eta$  levels, or let the real program do it for you
- Verify that the *"thicknesses" are acceptable*, generally about the same value in the free-atmosphere and less than 1000 m
- It is *SAFEST to NOT initially choose eta values*
  - Initially, *select the number* of  $\eta$  levels
  - *Plot profiles* of the resultant heights
  - *Adjust the eta levels* accordingly
- A few namelist options, the terrain elevation, and eta levels completely define the model coordinate for the WRF code

## Vertical Interpolation


- The *eta surfaces* are computed with a few NML parameters:

```
&domains
e_vert      = 50,    50,    50
p_top_requested = 1000,

&dynamics
base_temp   = 290.
iso_temp    = 200
```

## Vertical Interpolation

Vertical cross sections of THICKNESS of each model layer, with 50 vertical levels above the PBL, ptop = 10 hPa.















## Physical Parameterization Settings

- The real program and the WRF model are tightly coupled
- Most physical parameterization settings in the namlist.input are IGNORED by real
- EXCEPT
  - *sf\_surface\_physics*
  - Land surface model (processes soil temperature and soil moisture)
  - Different schemes in WRF use *differing numbers of layers*
  - The layers are defined in real from the metgrid output

## Soil Level Interpolation











- The WRF model supports several Land Surface schemes:
  - sf\_surface\_physics = 1, Slab scheme
  - 5 layers
  - Defined with thicknesses: 1, 2, 4, 8, 16 cm

Noah		RUC	
Layers	Mid point	Levels	
	000 – 010 cm -- 005 cm		000 cm
	010 – 040 cm -- 025 cm		005 cm
	040 – 100 cm -- 070 cm		020 cm
			040 cm
			160 cm
	100 – 200 cm -- 150 cm		300 cm













## Soil Level Interpolation

- The WRF model supports several Land Surface schemes:
  - sf\_surface\_physics = 2, Unified Noah scheme
  - 4 layers
  - Defined with layers: 0-10, 10-40, 40-100, 100-200 cm

Noah		RUC	
Layers	Mid point	Levels	
 000 – 010 cm	-- 005 cm	 000 cm	
 010 – 040 cm	-- 025 cm	 005 cm	
 040 – 100 cm	-- 070 cm	 020 cm	
	100 – 200 cm	 040 cm	
		 160 cm	
		 300 cm	











## Soil Level Interpolation

- The WRF model supports several Land Surface schemes:
  - sf\_surface\_physics = 3, RUC scheme
  - 6 levels
  - Defined at levels: 0, 5, 20, 40, 160, 300 cm

Noah		RUC	
Layers	Mid point	Levels	
 000 – 010 cm	-- 005 cm	 000 cm	
 010 – 040 cm	-- 025 cm	 005 cm	
 040 – 100 cm	-- 070 cm	 020 cm	
	100 – 200 cm	 040 cm	
		 160 cm	
		 300 cm	

## Soil Level Interpolation

- The WRF model supports several Land Surface schemes:
  - sf\_surface\_physics = 7, PX scheme
  - 2 layers
  - Defined with layers: 0-1, 1-100 cm

Noah		RUC	
Layers	Mid point	Levels	
 000 – 010 cm	-- 005 cm	 000 cm	
 010 – 040 cm	-- 025 cm	 005 cm	
 040 – 100 cm	-- 070 cm	 020 cm	
	100 – 200 cm	 040 cm	
		 160 cm	
		 300 cm	

## Real program in a nutshell

- Function
- Standard input variables
- Base State
- Standard generated output
- Vertical interpolation
- Soil level interpolation

## Real namelist

- The real program and WRF model SHARE a namelist file: **namelist.input**
- Some entries are used by both programs: dimensions, starting date/time, LBC, FDDA
- Many entries are only for one of the programs: real does not care about advection, diffusion, DFI

```
WRFV3
/test
/em_real
/namelist.input
```

## Real namelist

- The **namelist.input** file is separated into separate namelist records, usually with related areas

**&time\_control** – dates, time, I/O  
**&domains** – domain grid sizes, REAL options  
**&physics** – land scheme and layers, land cats  
**&dynamics** – base state, GWD  
**&bdy\_control** – lateral boundary conditions

## Real namelist

```
&time_control
start_year      = 2017, 2008,
start_month     = 05,  01,
start_day       = 30,  01,
start_hour      = 12,  00,
end_year        = 2017, 2008,
end_month       = 05,  01,
end_day         = 30,  01,
end_hour        = 12,  00,
interval_seconds = 21600
input_from_file  = .t.,  .t.,
io_form_input    = 2
io_form_boundary = 2
```

## Real namelist

```
&time_control
start_year      = 2017, 2008,
start_month     = 05,  01,
start_day       = 30,  01,
start_hour      = 12,  00,
end_year        = 2017, 2008,
end_month       = 05,  01,
end_day         = 30,  01,
end_hour        = 12,  00,
interval_seconds = 21600
input_from_file  = .t.,  .t.,
io_form_input    = 2
io_form_boundary = 2
```

START:  
Same as metgrid

## Real namelist

```
&time_control
start_year      = 2017, 2008,
start_month     = 05, 01,
start_day       = 30, 01,
start_hour      = 12, 00,
end_year        = 2017, 2008,
end_month       = 05, 01,
end_day         = 30, 01,
end_hour        = 12, 00,
interval_seconds = 21600
input_from_file = .t., .t.,
io_form_input   = 2
io_form_boundary = 2
```

END:  
Same as metgrid

## Real namelist

```
&time_control
start_year      = 2017, 2008,
start_month     = 05, 01,
start_day       = 30, 01,
start_hour      = 12, 00,
end_year        = 2017, 2008,
end_month       = 05, 01,
end_day         = 30, 01,
end_hour        = 12, 00,
interval_seconds = 21600
input_from_file = .t., .t.,
io_form_input   = 2
io_form_boundary = 2
```

Interval:  
Same as metgrid

## Real namelist

```
&time_control
start_year      = 2017, 2008,
start_month     = 05, 01,
start_day       = 30, 01,
start_hour      = 12, 00,
end_year        = 2017, 2008,
end_month       = 05, 01,
end_day         = 30, 01,
end_hour        = 12, 00,
interval_seconds = 21600
input_from_file = .t., .t.,
io_form_input   = 2
io_form_boundary = 2
```

How many domains  
from geogrid and  
metgrid

## Real namelist

```
&time_control
start_year      = 2017, 2008,
start_month     = 05, 01,
start_day       = 30, 01,
start_hour      = 12, 00,
end_year        = 2017, 2008,
end_month       = 05, 01,
end_day         = 30, 01,
end_hour        = 12, 00,
interval_seconds = 21600
input_from_file = .t., .t.,
io_form_input   = 2
io_form_boundary = 2
```

Leave default = 2  
NETCDF

## Real namelist

```
&domains
max_dom          = 1,
e_we             = 74,   112,
e_sn             = 61,   97,
e_vert           = 30,   30,
p_top_requested  = 5000,
num_metgrid_levels = 27,
num_metgrid_soil_levels = 4,
dx              = 30000, 10000,
dy              = 30000, 10000,
grid_id         = 1,    2,
parent_id       = 0,    1,
i_parent_start  = 1,    31,
j_parent_start  = 1,    17,
parent_grid_ratio = 1,    3,
```

## Real namelist

```
&domains
max_dom          = 1,
e_we             = 74,   112,
e_sn             = 61,   97,
e_vert           = 30,   30,
p_top_requested  = 5000,
num_metgrid_levels = 27,
num_metgrid_soil_levels = 4,
dx              = 30000, 10000,
dy              = 30000, 10000,
grid_id         = 1,    2,
parent_id       = 0,    1,
i_parent_start  = 1,    31,
j_parent_start  = 1,    17,
parent_grid_ratio = 1,    3,
```

REAL: Total  
number of domains  
on INPUT

## Real namelist

```
&domains
max_dom          = 1,
e_we             = 74,   112,
e_sn             = 61,   97,
e_vert           = 30,   30,
p_top_requested  = 5000,
num_metgrid_levels = 27,
num_metgrid_soil_levels = 4,
dx              = 30000, 10000,
dy              = 30000, 10000,
grid_id         = 1,    2,
parent_id       = 0,    1,
i_parent_start  = 1,    31,
j_parent_start  = 1,    17,
parent_grid_ratio = 1,    3,
```

Domain size in grid  
cells (u,v,w)

## Real namelist

```
&domains
max_dom          = 1,
e_we             = 74,   112,
e_sn             = 61,   97,
e_vert           = 30,   30,
p_top_requested  = 5000,
num_metgrid_levels = 27,
num_metgrid_soil_levels = 4,
dx              = 30000, 10000,
dy              = 30000, 10000,
grid_id         = 1,    2,
parent_id       = 0,    1,
i_parent_start  = 1,    31,
j_parent_start  = 1,    17,
parent_grid_ratio = 1,    3,
```

Model lid (Pa)  
5000 Pa (20 km),  
No lower

## Real namelist

```
&domains
max_dom          = 1,
e_we             = 74,   112,
e_sn             = 61,   97,
e_vert           = 30,   30,
p_top_requested  = 5000,
num_metgrid_levels = 27,
num_metgrid_soil_levels = 4,
dx              = 30000, 10000,
dy              = 30000, 10000,
grid_id         = 1,    2,
parent_id       = 0,    1,
i_parent_start  = 1,    31,
j_parent_start  = 1,    17,
parent_grid_ratio = 1,    3,
```

Consistent with  
dimensions from  
metgrid

## Real namelist

```
&domains
max_dom          = 1,
e_we             = 74,   112,
e_sn             = 61,   97,
e_vert           = 30,   30,
p_top_requested  = 5000,
num_metgrid_levels = 27,
num_metgrid_soil_levels = 4,
dx              = 30000, 10000,
dy              = 30000, 10000,
grid_id         = 1,    2,
parent_id       = 0,    1,
i_parent_start  = 1,    31,
j_parent_start  = 1,    17,
parent_grid_ratio = 1,    3,
```

Grid distance (m)  
dx=dy, except for  
lat/lon domains

## Real namelist

```
&domains
max_dom          = 1,
e_we             = 74,   112,
e_sn             = 61,   97,
e_vert           = 30,   30,
p_top_requested  = 5000,
num_metgrid_levels = 27,
num_metgrid_soil_levels = 4,
dx              = 30000, 10000,
dy              = 30000, 10000,
grid_id         = 1,    2,
parent_id       = 0,    1,
i_parent_start  = 1,    31,
j_parent_start  = 1,    17,
parent_grid_ratio = 1,    3,
```

Parent/child  
information, same as  
metgrid

## Real namelist

```
&domains
max_dom          = 1,
e_we             = 74,   112,
e_sn             = 61,   97,
e_vert           = 30,   30,
p_top_requested  = 5000,
num_metgrid_levels = 27,
num_metgrid_soil_levels = 4,
dx              = 30000, 10000,
dy              = 30000, 10000,
grid_id         = 1,    2,
parent_id       = 0,    1,
i_parent_start  = 1,    31,
j_parent_start  = 1,    17,
parent_grid_ratio = 1,    3,
smooth_cg_topo  = .t.
```

With high topo on  
CG boundaries, turn  
this ON

## Real namelist

### &physics

```
sf_surface_physics = 2,      2,  
num_soil_layers    = 4,  
num_land_cat       = 21,  
sf_urban_physics   = 0,      0,
```

## Real namelist

### &physics

```
sf_surface_physics = 2,      2,  
num_soil_layers    = 4,  
num_land_cat       = 21,  
sf_urban_physics   = 0,      0,
```

Real and WRF have to be consistent with the surface layer scheme due to the dimensions of the soil temp and moisture

## Real namelist

### &physics

```
sf_surface_physics = 2,      2,  
num_soil_layers    = 4,  
num_land_cat       = 21,  
sf_urban_physics   = 0,      0,
```

The dimensions of the land categories must match the selected data source from geogrid

## Real namelist

### &physics

```
sf_surface_physics = 2,      2,  
num_soil_layers    = 4,  
num_land_cat       = 21,  
sf_urban_physics   = 0,      0,
```

Arrays between real and WRF need to be consistently dimensioned

### Real namelist

**&dynamics**

**base\_temp** = 290.

**gwd\_opt** = 1,

### Real namelist

**&dynamics**

**base\_temp** = 290.

**gwd\_opt** = 1,

Atmospheric  
temperature (K) at  
sea level (NOT SST)  
in the middle of  
your domain  
Must not change  
between real and  
WRF

### Real namelist

**&dynamics**

**base\_temp** = 290.

**gwd\_opt** = 1,

GWD allocates  
space which must be  
consistent between  
real and WRF

### Real namelist

**&bdy\_control**

**spec\_bdy\_width** = 5,

**spec\_zone** = 1,

**relax\_zone** = 4,

**specified** = .t., .f.,

**nested** = .f., .t.,



### Real namelist

```
&bdy_control  
spec_bdy_width = 5,  
spec_zone      = 1,  
relax_zone     = 4,  
specified      = .t., .f.,  
nested         = .f., .t.,
```

spec\_bdy\_width =  
spec\_zone +  
relax\_zone  
  
spec\_zone = 1

### Real namelist

```
&bdy_control  
spec_bdy_width = 5,  
spec_zone      = 1,  
relax_zone     = 4,  
specified      = .t., .f.,  
nested         = .f., .t.,
```

spec\_bdy\_width = 10,  
relax\_zone = 9,  
spec\_exp = 0.33

Can choose larger  
relaxation zone  
since domain is big

Can choose  
exponential decay

### Real namelist

```
&bdy_control  
spec_bdy_width = 5,  
spec_zone      = 1,  
relax_zone     = 4,  
specified      = .t., .f.,  
nested         = .f., .t.,
```

REAL:  
d01 always  
specified=T  
  
All other domains  
have specified=F

### Real namelist

```
&bdy_control  
spec_bdy_width = 5,  
spec_zone      = 1,  
relax_zone     = 4,  
specified      = .t., .f.,  
nested         = .f., .t.,
```

d01 always  
nested=F

All other domains  
have nested=T

## Real program in a nutshell: PART 2

- Access to everything
- Eta levels
- Metgrid flags
- Adding a variable for vertical interpolation
- Vertical interpolation
- Tracers
- Trajectories
- Options

## Access to Everything

- The primary location to modify the real program is the **dyn\_em/module\_initialize\_real.F** file
- Contains:
  - Registry information
  - All of the namelist settings selected
  - Variables **from** the metgrid program
  - Variables to be **sent to** the WRF model
- Called for **every time period**, for **every domain**

## Access to Everything

- The value of **every variable input** into the WRF model is controlled through module\_initialize\_real.F
- All variables are accessed through the **derived data type** “grid”

```
DO j=jts,MIN(jde-1,jte)
  DO i=its,MIN(ide-1,ite)
    grid%sst(i,j) = grid%sst(i,j) + 1
  END DO
END DO
```

## Access to Everything

- The dynamics variables have **two time levels**, indicated by the \_1 and \_2 suffixes. Only the \_2 variables are sent to WRF.
- Some variables sent to WRF are **diagnostic** only

```
DO j = jts, min(jde-1,jte)
  DO i = its, min(ide,ite)
    grid%u10(i,j)=grid%u_gc(i,1,j)
  END DO
END DO
```

## Eta Levels

- The **vertical coordinate**, eta, used in the WRF model is defined inside of the real program.
- The user may allow the real program to choose the levels (select only the number of levels in the namelist.input file)

**&domains**

```
e_vert      = 30,      30,      30,  
/
```

**&domains**

```
e_vert      = 30,      40,      50,  
/
```

## Eta Levels

- Often the user needs to **specify the eta levels** (coordinate this with your model top)
- Use the automatic generation to your advantage
- Specify how many levels **ABOVE the PBL** that you require. Add 8 to this value. For example, you require 50 vertical levels above the PBL.

**&domains**

```
e_vert      = 58,      58,      58,  
/
```

## Eta Levels

- Run the real program (single or **small domain, one time level**), make sure the level thicknesses are OK (< 1000 m)

Converged znw(kte) should be about 0.0 = -5.2081142E-04

Full level index = 1	Height = 0.0 m	Thickness = 56.6 m
Full level index = 2	Height = 56.6 m	Thickness = 81.4 m
Full level index = 3	Height = 137.9 m	Thickness = 106.8 m
Full level index = 4	Height = 244.7 m	Thickness = 132.9 m
Full level index = 5	Height = 377.6 m	Thickness = 168.7 m
Full level index = 6	Height = 546.3 m	Thickness = 214.8 m
Full level index = 7	Height = 761.1 m	Thickness = 255.0 m
Full level index = 8	Height = 1016.2 m	Thickness = 190.9 m
Full level index = 9	Height = 1207.1 m	Thickness = 194.6 m
Full level index = 10	Height = 1401.8 m	Thickness = 198.5 m
Full level index = 11	Height = 1600.3 m	Thickness = 202.5 m
Full level index = 12	Height = 1802.8 m	Thickness = 393.3 m
Full level index = 13	Height = 2196.1 m	

## Eta Levels

- Get the computed levels from ncdump, after running the real program

> **ncdump -v ZNW wrfinput\_d01**

data:

ZNW =

```
1, 0.993, 0.983, 0.97, 0.954, 0.934, 0.909, 0.88, 0.8587637, 0.8375274,  
0.8162911, 0.7950548, 0.7550299, 0.7165666, 0.6796144, 0.6441237,  
0.6100466, 0.5773363, 0.5459476, 0.5158363, 0.4869595, 0.4592754,  
0.4327437, 0.407325, 0.382981, 0.3596745, 0.3373697, 0.3160312,  
0.2956253, 0.2761188, 0.2574798, 0.2396769, 0.2226802, 0.2064602,  
0.1909885, 0.1762376, 0.1621807, 0.1487919, 0.1360459, 0.1239184,  
0.1124378, 0.1017038, 0.09166772, 0.08228429, 0.07351105, 0.06530831,  
0.05763897, 0.05046835, 0.04376402, 0.03749565, 0.0316349, 0.02615526,  
0.02103195, 0.01624179, 0.01176313, 0.007575703, 0.003660574, 0 ;
```

## Eta Levels

- Re-run the real program (all domains, all time periods) with the new levels in the nml variable **eta\_levels**
- Replace the **PBL values** with those of your choosing.
- Augment the number of vertical levels (e\_vert)
- Note that both e\_vert and eta\_levels are **full levels**

## Eta Levels

```
&domains
eta_levels =
  1, 0.993, 0.983, 0.97, 0.954, 0.934, 0.909, 0.88,
  0.8587637, 0.8375274,
  0.8162911, 0.7950548, 0.7550299, 0.7165666, 0.6796144, 0.6441237,
  0.6100466, 0.5773363, 0.5459476, 0.5158363, 0.4869595, 0.4592754,
  0.4327437, 0.407325, 0.382981, 0.3596745, 0.3373697, 0.3160312,
  0.2956253, 0.2761188, 0.2574798, 0.2396769, 0.2226802, 0.2064602,
  0.1909885, 0.1762376, 0.1621807, 0.1487919, 0.1360459, 0.1239184,
  0.1124378, 0.1017038, 0.09166772, 0.08228429, 0.07351105, 0.06530831,
  0.05763897, 0.05046835, 0.04376402, 0.03749565, 0.0316349, 0.02615526,
  0.02103195, 0.01624179, 0.01176313, 0.007575703, 0.003660574, 0
/
```

- Maybe replace with

```
1, 0.999, 0.998, 0.996, 0.993, 0.990, 0.980, 0.970, 0.960, 0.950,
  0.940, 0.930, 0.920, 0.910, 0.900, 0.890, 0.880, 0.870,
```

## Eta Levels

- For **vertical nesting refinement**, follow the similar procedure for each domain.
- **Each domain** will need a specification of eta levels
- The assignment of the single **eta\_levels array is split** into pieces for easier understanding

## Eta Levels

```
&domains
max_dom = 2,
e_vert = 35, 45,
eta_levels(1:35) = 1., 0.993, 0.983, 0.97, 0.954, 0.934,
  0.909, 0.88, 0.840, 0.801, 0.761, 0.722,
  0.652, 0.587, 0.527, 0.472, 0.421, 0.374,
  0.331, 0.291, 0.255, 0.222, 0.191, 0.163,
  0.138, 0.115, 0.095, 0.077, 0.061, 0.047,
  0.035, 0.024, 0.015, 0.007, 0.
eta_levels(36:81) = 1.0000, 0.9946, 0.9875, 0.9789, 0.9685,
  0.9562, 0.9413, 0.9238, 0.9037, 0.8813,
  0.8514, 0.8210, 0.7906, 0.7602, 0.7298,
  0.6812, 0.6290, 0.5796, 0.5333, 0.4901,
  0.4493, 0.4109, 0.3746, 0.3412, 0.3098,
  0.2802, 0.2524, 0.2267, 0.2028, 0.1803,
  0.1593, 0.1398, 0.1219, 0.1054, 0.0904,
  0.0766, 0.0645, 0.0534, 0.0433, 0.0341,
  0.0259, 0.0185, 0.0118, 0.0056, 0.
vert_refine_method = 0, 2,
```

## The metgrid Flags

- The **real program and the WRF model** are able to communicate directly through the **Registry** file
- The real program is only able to talk with the **metgrid** program through the **input data** stream
- Specific information about the incoming data is contained in **special flags** that the user may set in the metgrid table file – usually, related to THIS VARIABLE EXISTS

```
=====
name=PMSL
      interp_option=sixteen_pt+four_pt+average_4pt
      flag_in_output=FLAG_SLP
=====
```

## The metgrid Flags

```
> ncdump -h met_em.d01.2000-01-24_12:00:00.nc | grep FLAG
      :FLAG_METGRID = 1 ;
      :FLAG_EXCLUDED_MIDDLE = 0 ;
      :FLAG_SOIL_LAYERS = 1 ;
      :FLAG_SNOW = 1 ;
      :FLAG_PSFC = 1 ;
      :FLAG_SM000010 = 1 ;
      :FLAG_SM010040 = 1 ;
      :FLAG_SM040100 = 1 ;
      :FLAG_SM100200 = 1 ;
      :FLAG_ST000010 = 1 ;
      :FLAG_ST010040 = 1 ;
      :FLAG_ST040100 = 1 ;
      :FLAG_ST100200 = 1 ;
      :FLAG_SLP = 1 ;
      :FLAG_TAVGSFC = 1 ;
      :FLAG_QNWFA = 1 ;
      :FLAG_QNIFA = 1 ;
      :FLAG_SOILHGT = 1 ;
      :FLAG_MF_XY = 1 ;
```

## The metgrid Flags

- The real program uses this **information** when deciding how to do many operations:
  - Is the input from metgrid?
  - Method to compute surface pressure
  - Use RH vs mixing ratio vs specific humidity computations
  - Excluded middle processing
  - Average surface air temperature for lake temperatures
  - Water/Ice friendly vertical interpolation
  - Which levels of soil data are present
- All **flags** for the metgrid to real data transfer are contained in **share/module\_optional\_input.F**

## The metgrid Flags

```
flag_slp      = 0

flag_name(1:8) = 'SLP      '
CALL wrf_get_dom_ti_integer ( fid, 'FLAG_' // &
                             flag_name, itmp, 1, icnt, ierr )
IF ( ierr .EQ. 0 ) THEN
    flag_slp      = itmp
END IF
```

## Adding a Variable for Vertical Interpolation

- This process is **manual**
- Every new **input 3d variable** that needs to be interpolated needs to have an **explicit block of code** added
- **Mass-point variables** (such as would be used in all physics schemes) are straight forward, as they may be largely copied using the existing templates already in place
- Most vertical interpolation options are supplied from the namelist.input file
- All interpolation is handled in **dry pressure**

## Adding a Variable for Vertical Interpolation

```
CALL vert_interp ( grid%t_gc , grid%pd_gc , &
  grid%t_2 , grid%pb , &
  grid%tmaxw , grid%ttrop , grid%pmaxw , grid%ptrop , &
  grid%pmaxwnn , grid%ptropnn , &
  flag_tmaxw , flag_ttrop , &
  config_flags%maxw_horiz_pres_diff , &
  config_flags%trop_horiz_pres_diff , &
  config_flags%maxw_above_this_level , &
  num_metgrid_levels , 'T' , &
  interp_type , lagrange_order , t_extrap_type , &
  lowest_lev_from_sfc , use_levels_below_ground , &
  use_surface , zap_close_levels , force_sfc_in_vinterp , &
  ids , ide , jds , jde , kds , kde , &
  ims , ime , jms , jme , kms , kme , &
  its , ite , jts , jte , kts , kte )
```

## Tracers

- The WRF model is able to **advect arrays of passive scalars** (tracer 4d array)
- As with all other variables going into the WRF model, this data is available to **be set in the real program**
- These variables must be **coordinated with the Registry names**, as the tracer index is an automatically manufactured name

```
# Tracer Scalars
```

```
#
```

```
state real tr17_1 ikjftb tracer 1 - irhusdf=(bdy_interp:dt) \
  "tr17_1" "tr17_1" "Dimensionless"
```

## Tracers

- As with all 4d arrays, no space is allocated unless the packaged variables are requested for processing at run-time

```
package tracer_test1 tracer_opt==2 - tracer:tr17_1
```

## Tracers

```
! Template for initializing tracer arrays.
! A small plane in the middle of the domain at
! lowest model level is defined.

IF (config_flags%tracer_opt .eq. 2) THEN
  DO j = (jde + jds)/2 - 4, (jde + jds)/2 + 4, 1
    DO i = (ide + ids)/2 - 4, (ide + ids)/2 + 4, 1
      IF ( ( its .LE. i .and. ite .GE. i ) .and. &
        ( jts .LE. j .and. jte .GE. j ) ) THEN
        tracer(i, 1, j, P_tr17_1) = 1.
      END IF
    END DO
  END DO
END IF
```

## Trajectories

- The user may **specify (i,j,k) locations** in the model domain to follow parcels: traj\_i, traj\_j, traj\_k (hard coded in the module\_initialize\_real.F file)
- The current **number of trajectory locations** is small, 25, and is a run-time option that the **user sets in the nml file**

```
&domain
  num_traj          = 25,

&physics
  traj_opt          = 1,
```

## Trajectories

- The trajectory code uses the lat,lon locations, so the initial (i,j) value of the lat,lon is assigned

```
IF (config_flags%num_traj .gt. 0 .and.
  config_flags%traj_opt .gt. 0) THEN
  DO j = (jde + jds)/2 - 2, (jde + jds)/2 + 2, 1
    DO i = (ide + ids)/2 - 2, (ide + ids)/2 + 2, 1
      IF ( its .LE. i .and. ite .GE. i .and. &
        jts .LE. j .and. jte .GE. j ) THEN
        grid%traj_i (icount) = i
        grid%traj_j (icount) = j
        grid%traj_k (icount) = 10
        grid%traj_lat (icount) = grid%xlai(i,j)
        grid%traj_long(icount) = grid%xlai(i,j)
      END IF
    END DO
  END DO
```

## Options

- When there are **strong normal topo gradients** along the outer rows and columns of the most-coarse domain, smoothing the topography to match the incoming first guess data is a good idea.
- This is **the same** sort processing that is done to make the child and parent domains more consistent in the area of the **LBC** forcing

```
&domains
  smooth_cg_topo = .true.
/
```



## Options

- **Time varying fields** for longer simulations are available from the technique set up for “SST Update”
- A new field will be automatically added to the input file to the WRF model (provided by the real program) with a few changes to the Registry file (**Registry.EM\_COMMON**), specifying **stream 4**

```
state real my_new_field ij misc 1 - \  
i024rhdu "MY_NEW_FIELD" \  
"SOME DESCRIPTION" "SOME UNITS"
```

## Options

- Information for **using time varying data** is specified at run-time in the namelist file

```
&time_control  
  auxinput4_inname    = "wrflowinp_d<domain>"  
  auxinput4_interval  = 360  
  io_form_auxinput4   = 2  
  
&physics  
  sst_update           = 1
```

## Real program in a nutshell: PART 2

- Access to everything
- Eta levels
- Metgrid flags
- Adding a variable for vertical interpolation
- Vertical interpolation
- Tracers
- Trajectories
- Options

## Real program in a nutshell: PART 2

- **Access to everything**      **The Derived Data Type: grid**
- Eta levels
- Metgrid flags      **Example: grid%sst**
- Adding a variable for vertical interpolation
- Vertical interpolation
- Tracers
- Trajectories
- Options

## Real program in a nutshell: PART 2

- Access to everything      Completely user defined
- Eta levels
- Metgrid flags      May be different per domain
- Adding a variable for vertical interpolation
- Vertical interpolation
- Tracers      Be careful of the thicknesses
- Trajectories
- Options      Tightly coupled with the model lid

## Real program in a nutshell: PART 2

- Access to everything      The metgrid program provides flags for some internal communication real to metgrid
- Eta levels
- Metgrid flags
- Adding a variable for vertical interpolation
- Vertical interpolation
- Tracers      These flags are defined inside the METGRID.TBL file (for WPS) and in the file share/module\_optional\_input.F (real)
- Trajectories
- Options

## Real program in a nutshell: PART 2

- Access to everything      Requires new code inside real
- Eta levels      Examples are easily available
- Metgrid flags
- Adding a variable for vertical interpolation
- Vertical interpolation
- Tracers
- Trajectories
- Options

## Real program in a nutshell: PART 2

- Access to everything      Always in dry pressure
- Eta levels
- Metgrid flags      Input vertical coordinate neutral
- Adding a variable for vertical interpolation
- Vertical interpolation
- Tracers
- Trajectories
- Options

## Real program in a nutshell: PART 2

- Access to everything
  - Eta levels
  - Metgrid flags
  - Adding a variable for vertical interpolation
  - Vertical interpolation
  - Tracers
  - Trajectories
  - Options
- Simple way to initialize passive scalars
- Users should provide info for which tracers in the Registry, and select the accompanying option in the namelist

## Real program in a nutshell: PART 2

- Access to everything
  - Eta levels
  - Metgrid flags
  - Adding a variable for vertical interpolation
  - Vertical interpolation
  - Tracers
  - Trajectories
  - Options
- A simple (i,j,k) initialization for the starting locations of trajectory points is available
- Choose the number of trajectory points

## Real program in a nutshell: PART 2

- Access to everything
  - Eta levels
  - Metgrid flags
  - Adding a variable for vertical interpolation
  - Vertical interpolation
  - Tracers
  - Trajectories
  - Options
- Users may smooth the outer rows and columns so that the topography on the coarse grid and the external model are consistent
- Users may add variables to streams easily, an example is that the SST update option could have a new field included (for example, soil moisture)